

z/VM



Guide for Automated Installation and Service

version 6 release 1

z/VM



Guide for Automated Installation and Service

version 6 release 1

Note:

Before using this information and the product it supports, read the information in “Notices” on page 221.

This edition applies to the version 6, release 1, modification 0 of IBM z/VM (product number 5741-A07) and to all subsequent releases and modifications until otherwise indicated in new editions.

This edition replaces GC24-6099-05.

© **Copyright International Business Machines Corporation 1991, 2009.**

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

Figures	vii
Tables	ix
About This Document	xi
Intended Audience	xi
Conventions and Terminology	xi
Where to Find More Information	xii
How to send your comments to IBM	xiii
If you have a technical problem	xiii
Summary of Changes	xv
GC24-6197-00, z/VM Version 6 Release 1	xv

Part 1. z/VM System DDR Installation 1

Chapter 1. Plan Your DDR Installation	3
Step 1. Review and Comply with the Requirements	4
Step 2. Complete the Installation and Basic IP Connectivity Worksheets	5
Worksheets	7
Chapter 2. First-Level DDR Installation Method	11
Step 1. Restore the Initial Installation System (IIS)	12
Step 2. IPL z/VM IIS	19
Step 3. Run INSTPLAN	23
Step 4. Run INSTVM	25
Step 5. Run SERVICE	29
Step 6. Run PUT2PROD	31
Step 7. Shut Down and Re-IPL the System	33
Chapter 3. Second-Level DDR Installation Method	35
Step 1. Load the Installation Tools from the z/VM System DDR	36
Step 2. Run INSTPLAN	38
Step 3. Restore the Initial Installation System (IIS)	40
Step 4. IPL z/VM IIS	42
Step 5. Run INSTVM	46
Step 6. Run SERVICE	50
Step 7. Run PUT2PROD	53
Step 8. Shut Down and Re-IPL the System	55

Part 2. z/VM System Image DVD Installation 57

Chapter 4. Plan Your DVD Installation	59
Step 1. Review and Comply with the Requirements	60
Step 2. Complete the Installation and Basic IP Connectivity Worksheets	62
Worksheets	64
Chapter 5. First-Level DVD Installation Method	67
Step 1. Load the RAMDISK	68
Step 2. Run INSTPLAN	71
Step 3. Verify the Volumes Needed for Installation are Available	73

Step 4. Run INSTDVD	75
Step 5. IPL the new z/VM System	78
Step 6. Run INSTVM	82
Step 7. Run SERVICE	85
Step 8. Run PUT2PROD	87
Step 9. Shut Down and Re-IPL the System	89
Chapter 6. Second-Level DVD Installation Method	91
From a DVD Drive	92
Step 1. Set up the User ID for Installation	92
Step 2. Run DVDPRIME	94
From an FTP Server Directory	96
Step 1. Set up the User ID for Installation	96
Step 2. Run DVDPRIME	98
From a VM Minidisk	100
Step 1. Set up the User ID for Installation	100
Step 2. Run DVDPRIME	105
Chapter 7. Load the System Image	107
Step 1. Run INSTPLAN	108
Step 2. Verify the Volumes Needed for Installation are Available	110
Step 3. Run INSTDVD.	112
Step 4. IPL the new z/VM System	116
Step 5. Run INSTVM	120
Step 6. Run SERVICE.	123
Step 7. Run PUT2PROD.	125
Step 8. Shut Down and Re-IPL the System	127

Part 3. Post z/VM System Installation 129

Chapter 8. Configure and Back Up the System	131
Step 1. Configure TCP/IP for an Initial Network Connection	132
Step 2. Back up the Named Saved Systems and Segments to Tape	134
Step 3. Back up the z/VM System to Tape	135
Step 4. Back up the z/VM System to DASD	138
Step 5. Create an IPLable DDR Utility Tape	140
Step 6. Create an IPLable ICKDSF Utility Tape	141
Step 7. Create a Stand-alone Dump Tape	143
Chapter 9. Plan Your Migration	145
Migration Overview	146
Step 1. Review and Comply with the Requirements	147
Step 2. Complete the Migration Worksheet	149
Chapter 10. Set Up for Migration	151
Step 1. IPL the new z/VM System	152
Step 2. Run MIGSETUP	156
Step 3. Run MIGLINK	157
Step 4. IPL the new z/VM System	158
Chapter 11. Migrate	161
Step 1. Run MIGRATE	162
Step 2. View the MIGRATE Message Log	163
Chapter 12. Place Migrated Parts into Production	165
Step 1. Run PUT2PROD.	166

Step 2. Shut Down the new System.	167
Step 3. Run MIGCLEAN	168
Step 4. Access Current System Software Inventory Disk	169
Step 5. IPL the new System	170
Step 6. Run MIGR51D	173
Additional Information	177
Chapter 13. Preinstalled Licensed Products and Features	179
Directory Maintenance Facility	179
Environmental Record Editing and Printing Program.	179
Hardware Configuration Definition and Hardware Configuration Manager for z/VM	180
Device Support Facilities (ICKDSF)	180
Open Systems Adapter Support Facility	180
Performance Toolkit for VM	181
RACF Security Server for z/VM	181
Remote Spooling Communications Subsystem (RSCS) Networking for z/VM	181
Transmission Control Protocol/Internet Protocol for z/VM	182

Part 4. Service Procedure 183

Chapter 14. Install Preventive (RSU) or Corrective (COR) Service and Place the Service into Production	185
Step 1. Load the Service Files from the RSU or COR	186
Step 2. Place the Service into Production.	189

Part 5. Appendixes 191

Appendix A. Setting up VMSES/E Licensed Products to use SERVICE	193
Appendix B. Determining the RSU Level for Ordering Service.	195
Appendix C. Migrate 51D from the Old System	197
Appendix D. Apply or Rework Local Service and Modifications	199
Apply or Create a Local Modification	199
Rework a Local Modification	200
Apply Local Service.	201
Appendix E. Contents of the z/VM System	203
Products Loaded from the z/VM System Installation Media	203
CMS Defaults	203
CP Defaults	203
GCS Defaults	204
Saved Segments on the z/VM System	205
VMSERVS, VMSERVU, and VMSERVER File Pool Defaults	205
VMSYS File Pool	206
Appendix F. Restore the Named Saved Systems and Segments from Tape	207
Appendix G. Restore the z/VM System Backup from Tape	209
Appendix H. Recover a File or Minidisk	211
Appendix I. Using an Integrated 3270 Console for Installation.	215

Appendix J. Using a Terminal Emulator to Upload Files from a DVD	219
Notices	221
Trademarks.	222
Glossary	225
Bibliography	227
Where to Get z/VM Information	227
z/VM Base Library	227
Overview	227
Installation, Migration, and Service	227
Planning and Administration.	227
Customization and Tuning	227
Operation and Use	227
Application Programming.	227
Diagnosis	228
z/VM Facilities and Features	228
Data Facility Storage Management Subsystem for VM	228
Directory Maintenance Facility for z/VM	228
Open Systems Adapter/Support Facility	228
Performance Toolkit for VM	229
RACF Security Server for z/VM	229
Remote Spooling Communications Subsystem Networking for z/VM	229
Prerequisite Products	229
Device Support Facilities	229
Environmental Record Editing and Printing Program.	229
Index	231

Figures

1. Sample Stand Alone Program Loader Panel	19
2. Installation Planning Panel	38
3. Installation DASD Format and Restore Panel (3390 Model Layout)	40
4. Sample Stand Alone Program Loader Panel	43
5. Installation Planning Panel	71
6. z/VM DVD Install Format and Restore Panel (3390 Model Layout)	75
7. Sample Stand Alone Program Loader Panel	79
8. Installation Planning Panel	94
9. DVDPRIME Panel	98
10. Installation Planning Panel	108
11. z/VM DVD Install Format and Restore Panel (3390 Model Layout)	112
12. Sample Stand Alone Program Loader Panel	117
13. Sample Stand Alone Program Loader Panel	153
14. Sample Stand Alone Program Loader Panel	159
15. Sample Stand Alone Program Loader Panel	171

Tables

1. DDR Installation Worksheet	7
2. DDR Installation TCP/IP Configuration Worksheet	8
3. QDIO Interface Worksheet (DDR Installation)	8
4. LCS Interface Worksheet (DDR Installation)	9
5. HiperSockets Interface Worksheet (DDR Installation)	9
6. CLAW Interface Worksheet (DDR Installation)	9
7. CTC Interface Worksheet (DDR Installation)	9
8. DVD Installation Worksheet	64
9. SCSI Device Definition Worksheet (DVD Installation)	64
10. DVD Installation TCP/IP Configuration Worksheet	65
11. QDIO Interface Worksheet (DVD Installation)	65
12. LCS Interface Worksheet (DVD Installation)	66
13. HiperSockets Interface Worksheet (DVD Installation)	66
14. CLAW Interface Worksheet (DVD Installation)	66
15. CTC Interface Worksheet (DVD Installation)	66
16. Migration Worksheet	149
17. Preinstalled Licensed Products and Features	179
18. Components, Features, and Products Supported by SERVICE and PUT2PROD	183
19. VMSYS File Pool User Ids	206

About This Document

This document guides anyone installing or servicing version 6 release 1 of IBM® z/VM® through step-by-step installation and service procedures. The procedures cover installation of a z/VM system first-level (on a processor) or second-level (as a guest operating system hosted by z/VM) from tape or DVD source.

You may treat each task in this document independently, but within each task read and follow the procedures in the order presented. For instance, if installing from tape, follow Part 1, “z/VM System DDR Installation,” on page 1. If installing from DVD, follow Part 2, “z/VM System Image DVD Installation,” on page 57. If migrating customized files and service for products pre-installed on z/VM installation media, follow Part 3, “Post z/VM System Installation,” on page 129. For information about customizing or configuring certain licensed products and features, follow Part 3, “Post z/VM System Installation,” on page 129. For service, follow Part 4, “Service Procedure,” on page 183.

Note: See *z/VM: General Information* for a list of the processors supported by z/VM and the guest operating systems hosted by z/VM.

Intended Audience

This information is intended for anyone responsible for installing or servicing z/VM.

A general knowledge of what z/VM does and an understanding of virtual machine concepts is required for getting the most out of this information. You should also have a general understanding of z/VM and System z™ data processing techniques and z/VM commands.

Conventions and Terminology

Various conventions are used to depict what you should type and what system responses you might see. Procedures will use the following conventions:

- The procedures in this document are in a two-column format. The left column shows the representative sequence of user entries and system responses, the right column contains explanatory comments and instructions about the entries shown in the left column.

Example:

attach *tapeaddr* * 181

TAPE *tapeaddr* ATTACHED TO *userID* 181
Ready; T=*n.nn/n.nn hh:mm:ss*

tapeaddr

is the address of the tape drive where the z/VM system DDR tape will be mounted.

userID

is the first-level user ID logged on to in the previous substep.

- Normal font indicates system responses and requests.

Example: The following shows a system response:

```
HCPIPX8475I THE PRODUCTS YOU SELECTED TO LOAD TO MINIDISK ARE:  
          VM RSCS TCPIP OSA ICKDSF DIRM RACF  
          PERFTK VMHCD
```

- Bold font indicates exactly what you should type.

Example: The following shows a command you would type:

disconnect

- Italic font indicates variable input or output, which can occur in commands you type or in system output.

Examples: The following are examples in which italics indicate variable input or output:

- In the following, you would need to supply the address of a tape drive for *tapeaddr*:
`attach tapeaddr * 181`
- In the following, the system would supply a tape address for *tapeaddr* and *userID* in its response:
`TAPE tapeaddr ATTACHED TO userID 181`

- Reverse type indicates special keys you must press.

Example: The following indicates you must press Enter:

ENTER

- A vertical bar (|) indicates you will receive or enter one of the values within the braces ({}).

Example: The following indicates sample output where you might receive one of two responses:

```
{MDREST|ECKDREST}: WROTE nnnn {BLOCKS|TRACKS} ON addr, RC=0
```

In this example, you would actually receive *one* of the following two responses:

```
MDREST: WROTE nnnn BLOCKS ON addr, RC=0
```

```
ECKDREST: WROTE nnnn TRACKS ON addr, RC=0
```

Where to Find More Information

This document includes all updates available at the time of publication. Any updates to this document will be reflected in the copy available in the z/VM Internet Library: www.ibm.com/eserver/zseries/zvm/library/.

For information about related documents, see “Bibliography” on page 227.

Links to Other Online Documents

If you are viewing the Adobe® Portable Document Format (PDF) version of this document, it might contain links to other documents. A link to another document is based on the name of the requested PDF file. The name of the PDF file for an IBM document is unique and identifies the edition. The links provided in this document are for the editions (PDF names) that were current when the PDF file for this document was generated. However, newer editions of some documents (with different PDF names) might exist. A link from this document to another document works only when both documents reside in the same directory.

How to send your comments to IBM

We appreciate your input on this publication. Feel free to comment on the clarity, accuracy, and completeness of the information or give us any other feedback that you might have.

Use one of the following methods to send us your comments:

1. Send an e-mail to mhvcfs@us.ibm.com
2. Visit the z/VM reader's comments Web page at www.ibm.com/systems/z/os/zvm/zvmforms/webqs.html
3. Mail the comments to the following address:
IBM Corporation
Attention: MHVRCFS Reader Comments
Department H6MA, Mail Station P181
2455 South Road
Poughkeepsie, NY 12601-5400
U.S.A.
4. Fax the comments to us as follows:
From the United States and Canada: 1+845+432-9405
From all other countries: Your international access code +1+845+432-9405

Include the following information:

- Your name and address
- Your e-mail address
- Your telephone or fax number
- The publication title and order number:
z/VM V6R1 Guide for Automated Installation and Service
GC24-6197-00
- The topic and page number related to your comment
- The text of your comment

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate without incurring any obligation to you.

IBM or any other organizations will only use the personal information that you supply to contact you about the issues that you submit to IBM.

If you have a technical problem

Do not use the feedback methods listed above. Instead, do one of the following:

- Contact your IBM service representative.
- Contact IBM technical support.
- Visit the z/VM support Web page at www.vm.ibm.com/service/
- Visit the IBM mainframes support Web page at www.ibm.com/systems/support/z/

Summary of Changes

This document contains terminology, maintenance, technical, and editorial changes. Some program updates might be provided through z/VM service by program temporary fixes (PTFs) for authorized program analysis reports (APARs), which also might be available for some prior releases.

For general installation changes in previous releases of z/VM, see Installation, Migration, and Service in *z/VM: Migration Guide*.

GC24-6197-00, z/VM Version 6 Release 1

This edition supports the general availability of z/VM V6.1.

- German is no longer an available default system language.
- The following new releases are preinstalled.
 - Directory Maintenance Facility, function level 610 (disabled)
 - Performance Toolkit for VM™, function level 610 (disabled)
 - RACF Security Server for z/VM, function level 610 (disabled)
 - RSCS Networking for z/VM, function level 610 (disabled)
 - TCP/IP, function level 610

Part 1. z/VM System DDR Installation

Part 1 contains procedures for installing z/VM from tape distribution media. If you are installing z/VM from DVD distribution media, use Part 2, “z/VM System Image DVD Installation,” on page 57.

In this part, you will:

- Plan your installation from tape.
- Fill in worksheets.
- Install the z/VM System image from tape.

Chapter 1. Plan Your DDR Installation

In this chapter, you will

- Plan your installation.
- Fill in the installation worksheet and the TCP/IP configuration worksheet.

Step 1. Review and Comply with the Requirements

Before you install z/VM version 6 release 1, you must satisfy the following requirements:

1. z/VM media deliverable
 - Be sure you have both the installation tape and the latest RSU tape(s).
 - If installing first-level, you cannot use electronic or CD-ROM service until after you have completed your installation. You need to install the RSU provided on tape.
 - If installing second-level and the RSU (or COR) service is electronic or on CD-ROM, you need to receive the service files to a minidisk attached to your installation user ID on your first-level system before IPLing your second-level system. Follow the instructions included with the electronic or CD-ROM service files to receive and restore the service files to a minidisk that can be temporarily attached to your second-level system.
2. General
 - A processor supported by z/VM version 6 release 1. For a list of processors supported by z/VM, see *z/VM: General Information*.
 - A local non-SNA 3270 terminal or equivalent, configured with at least 24 lines, or an integrated 3270 console.
 - For instructions on how to receive up-to-date service, see the Program Directory for z/VM.
 - For up-to-date information affecting installation, see the "installation information" section in the CP subset of the zvm610 upgrade PSP bucket.
 - If you plan to migrate from another z/VM system, review *z/VM: Migration Guide*.
 - If you plan to deploy Linux[®] on z/VM, see *z/VM: Getting Started with Linux on System z* for important planning information about Linux virtual servers.
3. First-level installation
 - At least 256 MB of real storage. Note that storage required for installation is not necessarily the amount you should have assigned for running production workloads. See *z/VM: CP Planning and Administration* for information on determining production storage requirements.
 - The function to change the installation pack labels cannot be used on a first-level installation from tape.
4. Second-level installation
 - You must IPL the z/VM Initial Installation System (IIS) using the same installation user ID you used to run INSTPLAN and INSTIIS.
 - The installation user ID must meet the following requirements:
 - At least 64 MB of virtual storage.
 - Privilege classes B and G.
 - Write access to a 191 minidisk with at least 500 4-KB blocks of available space. A shared file system directory cannot be used.
 - To change installation DASD labels, the installation user ID must be able to issue the DEFINE MDISK command. The IBM default privilege class for this command is class A. The DEFINE MDISK command also requires the user ID to have DEVMAINT on the OPTION directory statement in its directory entry.

Step 2. Complete the Installation and Basic IP Connectivity Worksheets

1. Determine the installation method you will use.
 - Choose first-level installation if no supported z/VM system is running on the processor or LPAR on which you are installing.
 - Choose second-level installation if you are installing in a virtual machine on a supported z/VM system.
2. Record the selected installation method (first-level or second-level) on the installation worksheet (Table 1 on page 7).
3. Determine which products you will load into the VMSYS file pool and which products you will load to minidisks only. Each product on the z/VM system DDR allows VMSYS file pool directories to be used in place of some minidisks. Record your choices under the Install To column on the installation worksheet (Table 1 on page 7).
4. Select your system default language and record your choice in the installation worksheet (Table 1 on page 7). The choices are:
 - Mixed Case English (AMENG)
 - Uppercase English (UCENG)
 - Kanji (KANJI)
5. Select the DASD model you will use to install, either 3390 Model 3 or 3390 Model 9, and record the DASD model in the installation worksheet (Table 1 on page 7). For performance reasons, if installing to 3390 Model 9, IBM recommends using emulated 3390 Model 9s instead of real 3390 Model 9s.

Notes:

- a. DASD size is not checked during installation.
 - b. If you select 3390 Model 3, installation uses the first 3338 cylinders on each DASD and ignores any cylinders beyond 3338.
 - c. If you select 3390 Model 9, installation uses the first 10017 cylinders on each DASD and ignores any cylinders beyond 10017.
6. Estimate the number of DASD volumes required to install. If you choose:
 - 3390 Model 3, you will need five volumes.
 - 3390 Model 9, you will need three volumes.

If you selected to install products to a combination of the VMSYS file pool and minidisks in substep 3, you might need an extra volume depending on where you choose to install each product.

Note: INSTPLAN, which is run early in the installation procedure, will tell you exactly how many volumes are required.

7. Record the address for each DASD under the *DASD Address* column on the installation worksheet (Table 1 on page 7). Record the first address in the row with the label 610RES and continue recording addresses corresponding to each label. Disregard any DASD labels that you do not need.
8. If you are changing a default installation DASD label, record the new label in the *New Label* column on the installation worksheet (Table 1 on page 7). The 610RES label cannot be changed.

Notes:

- a. Installation DASD labels cannot be changed on a first-level installation from tape.
- b. To change installation DASD labels, the installation user ID must be able to issue the DEFINE MDISK command. The IBM default privilege class for this command is class A. The DEFINE MDISK command also requires the user ID to have DEVMAINT on the OPTION directory statement in its directory entry.

Complete the Installation and Basic IP Connectivity Worksheets

9. If, after you install z/VM, you want to establish a minimal TCP/IP configuration that establishes basic connectivity to your IP network, fill in the IP worksheets beginning with Table 2 on page 8 and then return here.

What to do next

Base your choice on the installation method that fits your situation.

If you chose the . . .	Then see. . .
First-level installation method	Chapter 2, "First-Level DDR Installation Method," on page 11
Second-level installation method	Chapter 3, "Second-Level DDR Installation Method," on page 35

Worksheets

Table 1. DDR Installation Worksheet

Installation method (first-level or second-level): _____					
Install To column: record an "M" if you will load the product to a minidisk or an "F" if you will load the product to the VMSYS file pool.					
Install To	Product	Install To	Product	Install To	Product
	VM		OSA		PERFTK
	VMHCD		RACF®		DIRM
	RSCS		ICKDSF		TCPIP
System default language: _____					
DASD type and model: _____					
Pack Type	DASD Label	New Label	DASD Address		
RES	610RES	610RES			
SPOOL	610SPL				
PAGE	610PAG				
USER1	610W01				
USER2	610W02				
USER3	610W03				

Note: Installation DASD labels cannot be changed on a first-level installation from tape.

Complete the Installation and Basic IP Connectivity Worksheets

After you have completed your z/VM installation, you can optionally create a minimal TCP/IP configuration that establishes basic connectivity to your IP network. If you choose to perform this configuration, you must gather the following information from your network system administrator and record the information in Table 2 and the appropriate interface worksheet. In these worksheets, a number in parentheses following a field description, for example Host name (20), is the maximum length for that field.

Note: The IP configuration wizard supports real network devices only. If you plan on using virtual network devices for TCP/IP, they must be configured manually. See *z/VM: TCP/IP Planning and Customization*.

Table 2. DDR Installation TCP/IP Configuration Worksheet

z/VM user ID of the z/VM TCP/IP stack virtual machine: (Default value is TCPIP. If you change this user ID, you must define the user ID in your user directory before running IPWIZARD.)	
Host name (20):	
Domain name (40):	
DNS IP address (up to three addresses):	1) _____ 2) _____ 3) _____
Gateway IP address :	
Interface name (16):	
Device number:	
IP address:	
IPv4 subnet mask (15) or IPv6 prefix length (3):	
Path MTU discovery (IPv4 interfaces):	<input type="checkbox"/> Enabled <input type="checkbox"/> Disabled
Choose the interface you will be using (check one):	<input type="checkbox"/> QDIO <input type="checkbox"/> LCS <input type="checkbox"/> HiperSockets <input type="checkbox"/> CLAW <input type="checkbox"/> CTC See the appropriate interface worksheet to record more information. IPv6 is available only for QDIO and HiperSockets devices.

Table 3. QDIO Interface Worksheet (DDR Installation)

Network type (select one):	<input type="checkbox"/> Ethernet <input type="checkbox"/> Token Ring IPv6 is not available for Token Ring adaptors.
Port name (optional) (8):	
Router type (select one):	<input type="checkbox"/> Primary <input type="checkbox"/> Secondary <input type="checkbox"/> None
Maximum transmission unit (MTU) size:	

Complete the Installation and Basic IP Connectivity Worksheets

Table 3. QDIO Interface Worksheet (DDR Installation) (continued)

Router advertisements (IPv6 only):	<input type="checkbox"/> On <input type="checkbox"/> Off
Port number (optional):	

Table 4. LCS Interface Worksheet (DDR Installation)

Network type (select one):	<input type="checkbox"/> Ethernet <input type="checkbox"/> Token Ring <input type="checkbox"/> FDDI
Port/adaptor number:	
Maximum transmission unit (MTU) size:	

Table 5. HiperSockets Interface Worksheet (DDR Installation)

Maximum frame size (MFS): (in kilobytes)	
Router advertisements (IPv6 only):	<input type="checkbox"/> On <input type="checkbox"/> Off

Table 6. CLAW Interface Worksheet (DDR Installation)

CLAW host name (8): (This name must match the host-name configured on the CLAW device)	
CLAW adapter name (8): (This name must match the device-name configured on the CLAW device)	
Maximum transmission unit (MTU) size:	

Table 7. CTC Interface Worksheet (DDR Installation)

Write channel device number (select one):	<input type="checkbox"/> This choice contains the device number specified on the main z/VM TCP/IP Configuration Wizard panel. <input type="checkbox"/> This choice contains the device number specified on the main z/VM TCP/IP Configuration Wizard panel plus 1.
Maximum transmission unit (MTU) size:	
Peer IP address:	

Complete the Installation and Basic IP Connectivity Worksheets

Chapter 2. First-Level DDR Installation Method

In this chapter, you will:

- Use step-by-step procedures to install the first-level z/VM system DDR in a new system environment.

Step 1. Restore the Initial Installation System (IIS)

In this step, you will:

- Mount the z/VM system DDR tape on a tape drive.
- Initialize, CP format, and relabel the DASD.
- Load IIS from the z/VM system DDR.

Notes:

1. The IPLable Device Support Facilities (ICKDSF) program in tape file 1 of the z/VM system DDR might not be at the latest service level. Use this copy of the program for installation only.
2. Make sure that any DASD with the same labels you are using for installation are not attached to your system.

1. Before you begin, fill out the installation worksheet (Table 1 on page 7) in Chapter 1, “Plan Your DDR Installation.”
2. Ensure all DASD addresses listed on the installation worksheet (Table 1 on page 7) are available for use. Follow the operation manual specific to your hardware.

Attention: Make sure any unused DASD with the label 610RES, 610SPL, 610PAG, or 610W0n are not attached to your system. Such DASD might be brought online when you IPL IIS in “Step 3. Restore the Initial Installation System (IIS)” on page 40. You can remove these DASD now or use the ICKDSF to relabel them. If you choose to relabel them, wait until substep 7 on page 13, which explains how to use ICKDSF to relabel DASD.

3. Mount the z/VM system DDR tape on a tape drive.
4. If you are installing from an integrated 3270 console, see Appendix I, “Using an Integrated 3270 Console for Installation,” on page 215.
5. IPL the tape drive to load ICKDSF. Specify a LOADPARM of CNSLccuu, where ccuu is the address of your system console (for example, 0020). For more information on performing a hardware IPL, see your processor's hardware operation manuals.

If you are using the integrated 3270 console, return to Appendix I, “Using an Integrated 3270 Console for Installation,” on page 215.

Note: For more information about ICKDSF, see *Device Support Facilities: User's Guide and Reference*.

6. Wait approximately 60 seconds for the IPL to complete. If you receive no messages, press Enter to create an interrupt. If you do not receive a response, you pressed Enter before the IPL was complete. Reset the keyboard. Wait approximately 60 seconds and press Enter again.

ENTER

CLEAR SCREEN WHEN READY

RESET

Press the key which corresponds to the reset function to unlock the keyboard.

CLEAR

Depending on how your console is defined, you might not have to clear your screen.

Restore the Initial Installation System (IIS)

```
ICK005E DEFINE INPUT DEVICE, REPLY
      'DDDD, CUU' OR 'CONSOLE'
ENTER INPUT/COMMAND:
```

ICK005E indicates ICKDSF is loaded and ready.

```
console
CONSOLE
ICK006E DEFINE OUTPUT DEVICE, REPLY
      'DDDD, CUU' OR 'CONSOLE'
ENTER INPUT/COMMAND:
console
CONSOLE
ICKDSF - SA/XA/ESA DEVICE SUPPORT FACILITIES
      nn.n TIME:hh:mm:ss mm/dd/yy   PAGE 1
ENTER INPUT/COMMAND:
```

7. If you do not have any DASD labeled 610RES, 610SPL, 610PAG, or 610W0n on your system or if all DASD labeled 610RES, 610SPL, 610PAG, and 610W0n are going to be used for installation, skip to substep 8. Otherwise, use ICKDSF to relabel of any DASD volumes that are not being used for the installation. If there is more than one DASD to relabel, relabel one at a time. Repeat this substep for each DASD to be relabeled.

```
cpvolume label unit(dasdaddr) novfy valid(valid)
ICK00700I DEVICE INFORMATION FOR dasdaddr IS
      CURRENTLY AS FOLLOWS:
      PHYSICAL DEVICE = xxxx.
      STORAGE CONTROLLER = xxxx
      STORAGE CONTROL DESCRIPTOR = xx
      DEVICE DESCRIPTOR = xx
      :
ICK003D REPLY U TO ALTER VOLUME dasdaddr CONTENTS,
      ELSE T
ENTER INPUT/COMMAND:
u
      :
ENTER INPUT/COMMAND:
```

dasdaddr
Address of the DASD to relabel.

valid
New label for *dasdaddr*.

8. If you have already initialized your DASD for this installation, skip to substep 9 on page 14 to format and label them. Otherwise, use the INSTALL command to initialize the DASD. If there is more than one uninitialized DASD, initialize one DASD at a time. Repeat this substep for each DASD to be initialized.

Note: Do not run the INSTALL command if using IBM System Storage™ DASD. IBM System Storage DASD are initialized when setup.

```
install unit(dasdaddr) novfy
ICK00700I DEVICE INFORMATION FOR dasdaddr IS
      CURRENTLY AS FOLLOWS:
      PHYSICAL DEVICE = xxxx.
      STORAGE CONTROLLER = xxxx
      STORAGE CONTROL DESCRIPTOR = xx
      DEVICE DESCRIPTOR = xx
      :
ICK003D REPLY U TO ALTER VOLUME dasdaddr CONTENTS,
      ELSE T
ENTER INPUT/COMMAND:
```

dasdaddr
Address of the DASD to initialize. This value is recorded on the installation worksheet (Table 1 on page 7).

Restore the Initial Installation System (IIS)

```
u
:
ENTER INPUT/COMMAND:
```

The system takes at least 20 to 40 minutes to inspect and initialize a DASD. You will get a series of ICK messages that describe the status of the device being initialized at the point that the initialization is almost complete.

9. If you have already CP formatted your DASD for this installation using ICKDSF or CPFMTXA, skip to substep 10 to label them. Otherwise, format and label each DASD listed on your installation worksheet (Table 1 on page 7). Repeat this substep for each DASD to be formatted and labeled. After all DASD have been formatted and labeled, continue with substep 11.

```
cpvolume format unit(dasdaddr) novfy valid(valid) mode(esa) nofiller
```

dasdaddr

Address of the DASD to format. This value is recorded on the installation worksheet.

valid

Volume identifier. This value (**DASD Label**) is recorded on the installation worksheet.

```

:
ICK003D REPLY U TO ALTER VOLUME dasdaddr CONTENTS,
      ELSE T
ENTER INPUT/COMMAND:
u
:
ENTER INPUT/COMMAND:
```

10. If you have already CP formatted and labeled your DASD in substep 9, skip to 11. Otherwise, label each DASD listed on the installation worksheet (Table 1 on page 7). Repeat this substep for each DASD to be labeled.

```
cpvolume label unit(dasdaddr) novfy valid(valid)
```

```
ICK00700I DEVICE INFORMATION FOR dasdaddr IS
      CURRENTLY AS FOLLOWS:
      PHYSICAL DEVICE = xxxx.
      STORAGE CONTROLLER = xxxx
      STORAGE CONTROL DESCRIPTOR = xx
      DEVICE DESCRIPTOR = xx
```

dasdaddr

Address of the DASD to relabel. This value is recorded on the installation worksheet.

valid

Volume identifier. This value (**DASD Label**) is recorded on the installation worksheet.

```

:
ICK003D REPLY U TO ALTER VOLUME dasdaddr CONTENTS,
      ELSE T
ENTER INPUT/COMMAND:
u
ENTER INPUT/COMMAND:
:
:
```

11. IPL the tape drive to load the DDR program. Specify a LOADPARM of *ccuu*, where *ccuu* is the address of your system console (for example, 0020). You do not have to exit ICKDSF. For more information on performing a hardware IPL, see your processor's hardware operation manuals. If you are using the integrated 3270 console, return to Appendix I, "Using an Integrated 3270 Console for Installation," on page 215.

Load parameter specified

If a console address is used, the DDR program will appear on the specified console.

Load parameter not specified

If no console address is used, you will need to wait approximately 60 seconds for the IPL to complete. You will receive no messages. Press Enter to create an interrupt. If you do not receive a response, you pressed Enter before the IPL was complete. Reset the keyboard. Wait approximately 60 seconds and press Enter again.

ENTER

CLEAR SCREEN WHEN READY

RESET

Press the Reset key to unlock the keyboard.

CLEAR

Depending on how your console is defined, you might not have to clear your screen.

12. Answer the following prompts from the DDR program to load IIS from the z/VM system DDR to 610RES and 610SPL.

z/VM DASD DUMP/RESTORE PROGRAM
ENTER CARD READER ADDRESS OR CONTROL STATEMENTS

ENTER:

sysprint cons

ENTER:

input tapeaddr tape (skip 1 leave

ENTER:

tapeaddr

Address of the tape drive where you mounted the z/VM system DDR tape.

By typing **tape**, the tape device type is automatically identified by the DDR program.

output dasdaddr dasd 610RES

dasdaddr

Address of 610RES. This value is recorded on the installation worksheet (Table 1 on page 7).

The DDR program verifies the DASD label is 610RES.

ENTER:

restore all

HCPDDR725D SOURCE DASD DEVICE WAS (IS) LARGER THAN OUTPUT DEVICE
DO YOU WISH TO CONTINUE? RESPOND YES OR NO:

yes

RESTORING 610RES

You might receive message HCP725D. If you do, it is not a problem. Respond **yes** and continue.

DATA DUMPED *mm/dd/yy*
AT *hh.mm.ss* GMT FROM 610RES
RESTORED TO 610RES

Notes:

1. GMT means Greenwich Mean Time.
2. The exact cylinder extents vary according to the device type.

Restore the Initial Installation System (IIS)

INPUT CYLINDER EXTENTS		OUTPUT CYLINDER EXTENTS	
START	STOP	START	STOP
0	158	0	158
399	685	399	685

END OF RESTORE
BYTES RESTORED *nnnnnnnnnn*
ENTER:
input *tapeaddr* **tape** (**rew**)
ENTER:

tapeaddr
Address of the tape drive where you mounted the z/VM system DDR tape.

By typing **tape**, the tape device type is automatically identified by the DDR program.

output *dasdaddr* **dasd** **610SPL**

dasdaddr
Address of 610SPL. This value is recorded on the installation worksheet (Table 1 on page 7).

The DDR program verifies the DASD label is 610SPL.

ENTER:
restore all
HCPDDR725D SOURCE DASD DEVICE WAS (IS) LARGER THAN OUTPUT DEVICE
DO YOU WISH TO CONTINUE? RESPOND YES OR NO:

yes
RESTORING 610SPL

You might receive message HCP725D. If you do, it is not a problem. Respond **yes** and continue.

DATA DUMPED *mm/dd/yy* AT *hh.mm.ss* GMT FROM 610SPL
RESTORED TO 610SPL

Notes:

1. GMT means Greenwich Mean Time.
2. The exact cylinder extents vary according to the device type.

INPUT CYLINDER EXTENTS		OUTPUT CYLINDER EXTENTS	
START	STOP	START	STOP
0	199	0	199

END OF RESTORE
BYTES RESTORED *nnnnnnnnnn*

ENTER:
ENTER
END OF JOB

Note: Give the tape time to rewind after the restore is complete.

Press Enter to end the program.

13. IPL the tape drive to load ICKDSF. Specify a LOADPARM of CNSL*ccuu*, where *ccuu* is the address of your system console (for example, 0020). For more information on performing a hardware IPL, see your processor's hardware operation manuals.

If you are using the integrated 3270 console, return to Appendix I, "Using an Integrated 3270 Console for Installation," on page 215.

Note: After the DDR program completes the restore, the tape is rewound to the beginning. If you have problems IPLing the tape, you might need to remount it.

14. Wait approximately 60 seconds for the IPL to complete. If you receive no messages, press Enter to create an interrupt. If you do not receive a response, you pressed Enter before the IPL was complete. Reset the keyboard. Wait approximately 60 seconds and press Enter again.

Restore the Initial Installation System (IIS)

ENTER

CLEAR SCREEN WHEN READY

RESET

Press the Reset key to unlock the keyboard.

CLEAR

Depending on how your console is defined, you might not have to clear your screen.

```
ICK005E DEFINE INPUT DEVICE, REPLY
      'DDDD,CUU' OR 'CONSOLE'
ENTER INPUT/COMMAND:
console
CONSOLE
ICK006E DEFINE OUTPUT DEVICE, REPLY
      'DDDD,CUU' OR 'CONSOLE'
ENTER INPUT/COMMAND:
console
CONSOLE
ICKDSF - SA/XA/ESA DEVICE SUPPORT FACILITIES
      nn.n TIME:hh:mm:ss mm/dd/yy PAGE 1
ENTER INPUT/COMMAND:
```

ICK005E indicates ICKDSF is loaded and ready.

15. Allocate the 610SPL and 610PAG DASD.

```
cpvolume alloc unit(dasdaddr) novfy type (SPOL, 200, endcyl)
```

dasdaddr

Address of 610SPL. This value is recorded on the installation worksheet (Table 1 on page 7).

endcyl

The last cylinder to allocate. The values are 3338 for a 3390 Model 3 and 10016 for a 3390 Model 9.

```
⋮
ICK003D REPLY U TO ALTER VOLUME dasdaddr CONTENTS,
      ELSE T
ENTER INPUT/COMMAND:
u
```

```
⋮
ENTER INPUT/COMMAND:
cpvolume alloc unit(dasdaddr) novfy type (PAGE, 1, endcyl)
```

dasdaddr

Address of 610PAG. This value is recorded on the installation worksheet (Table 1 on page 7).

endcyl

The last cylinder to allocate. The values are 3338 for a 3390 Model 3 and 10016 for a 3390 Model 9.

```
⋮
ICK003D REPLY U TO ALTER VOLUME dasdaddr CONTENTS,
      ELSE T
ENTER INPUT/COMMAND:
u
⋮
```

Restore the Initial Installation System (IIS)

16. If you selected to install on a 3390 Model 3, skip this substep. Otherwise, if you selected to install on a 3390 Model 9, allocate the 610RES DASD, increasing the allocation to the end of the volume.

```
cpvolume alloc unit(dasdaddr) novfy
```

```
  :  
ICK003D REPLY U TO ALTER VOLUME dasdaddr CONTENTS,  
      ELSE T
```

```
ENTER INPUT/COMMAND:
```

```
u
```

```
  :  
ENTER INPUT/COMMAND:
```

dasdaddr

Address of 610RES. This value is recorded on the installation worksheet (Table 1 on page 7).

Step 2. IPL z/VM IIS

In this step, you will:

- IPL z/VM IIS first-level.

1. IPL the initial system you restored. In the hardware Load panel, enter the real address of the 610RES volume, which you can find in the installation worksheet (Table 1 on page 7). Specify a LOADPARM of *ccuu*, where *ccuu* is the address of your system console (for example, 0020). For more information on performing a hardware IPL, see your processor's hardware operation manuals.

If you are using the integrated 3270 console, return to Appendix I, "Using an Integrated 3270 Console for Installation," on page 215.

The Stand Alone Program Loader panel is displayed on the specified operator console.

```

STAND ALONE PROGRAM LOADER: z/VM VERSION 6 RELEASE 1.0
DEVICE NUMBER:  dasdaddr  MINIDISK OFFSET:  nnnnnnnn  EXTENT:  1
MODULE NAME:    CLOAD    LOAD ORIGIN:      1000
-----IPL PARAMETERS-----
cons=consaddr
-----COMMENTS-----
-----
9= FILELIST  10= LOAD  11= TOGGLE EXTENT/OFFSET

```

Figure 1. Sample Stand Alone Program Loader Panel

2. Move the cursor to the IPL PARAMETERS field and type:

```
cons=consaddr
```

```
consaddr
```

Virtual console address. Spaces are not allowed around the equal sign. If you are using the integrated 3270 console, *consaddr* is SYSG.

3. Press F10 to load.

F10

hh:mm:ss z/VM V6 R1.0 SERVICE LEVEL nnnn (64-BIT)

hh:mm:ss SYSTEM NUCLEUS CREATED ON yyyy-mm-dd AT hh:mm:ss,
LOADED FROM 610RES

```
hh:mm:ss *****
hh:mm:ss * LICENSED MATERIALS - PROPERTY OF IBM* *
hh:mm:ss * 5741-A07 (C) COPYRIGHT IBM CORP. 1983, *
hh:mm:ss * 2009. ALL RIGHTS RESERVED. *
hh:mm:ss * US GOVERNMENT USERS RESTRICTED RIGHTS - *
hh:mm:ss * USE, DUPLICATION OR DISCLOSURE *
hh:mm:ss * RESTRICTED BY GSA ADP SCHEDULE CONTRACT *
hh:mm:ss * WITH IBM CORP. *
hh:mm:ss * *
hh:mm:ss * * TRADEMARK OF INTERNATIONAL BUSINESS *
hh:mm:ss * MACHINES *
hh:mm:ss *****
```

hh:mm:ss HCPZC06718I Using parm disk 1 on volume 610RES (device xxxx).

hh:mm:ss HCPZC06718I Parm disk resides on cylinders nnn through nnn.

⋮

You might receive an informational message, HCPISU951I, about volumes not mounted. If you are not using those volume labels, ignore this message.

Note: If you receive informational message HCPISU954I, you have duplicate volumes with the same label and must correct this error before continuing. Make a note of the duplicate DASD addresses.

To correct the duplicate volume error:

1. At the start prompt, enter SHUTDOWN.
2. Change the label of each DASD that is not to be used (see “Step 1. Restore the Initial Installation System (IIS)” on page 12, substeps 3 through 7).
3. IPL the system again (see “Step 2. IPL z/VM IIS” on page 19, substep 1).

hh:mm:ss Start ((Warm|Force|COLD|CLEAN) (DRain)
(DIisable) (NODIRect) (NOAUTOlog)) or (SHUTDOWN)

cold drain noauto1og

Because there is no data or accounting information to recover, use COLD DRAIN to request a cold start. Include NOAUTOLOG because you do not need the servers and all user IDs logged on.

4. If the time-of-day (TOD) clock is not already set, use standard operating procedures to set it. For more information, see *z/VM: System Operation*.

```
NOW hh:mm:ss {EST|EDT} weekday yyyy-mm-dd
Change TOD clock (yes|no)
{yes|no}
```

You will see this message if the TOD clock has already been set. Answer **yes** to reset the TOD clock, **no** to keep the current setting.

If you answered yes to resetting the TOD clock

Set date MM/DD/YY

Type in the month, day, and year, separated by slash marks.

Set time HH:MM:SS

Type in the hours, minutes, and seconds, separated by colons.

Press "TOD ENABLE SET" key at designated instant

NOW *hh:mm:ss* {EST|EDT} *weekday mm/dd/yy*

Change TOD clock (Yes|No)

no

If you are using a multiprocessor, you might receive a message concerning the clocks of the different processor images. If you do, see *z/VM: System Operation* for information about resetting the clocks.

CP logs on the primary system operator user ID (OPERATOR).

hh:mm:ss The directory on volume 610RES at address *nnnn* has been brought online.

hh:mm:ss HCPWRS2513I

hh:mm:ss HCPWRS2513I Spool files available {*nnnn*|NONE}

Note: Depending on the type of spool files available, you might receive the following prompt:

Spool files prompt

hh:mm:ss HCPWRS2513I

hh:mm:ss HCPWRS2513I Spool files on offline volumes {*nnnn*|NONE}

hh:mm:ss HCPWRS2513I Spool files with I/O errors {*nnnn*|NONE}

hh:mm:ss HCPWRS2513I Spool files with control errors {*nnnn*|NONE}

hh:mm:ss HCPWRS2513I Spool files to be discarded {*nnnn*|NONE}

hh:mm:ss HCPWRS2513I

hh:mm:ss HCPWRS2513I Total files to be deleted *nnnn*

hh:mm:ss HCPWRS2511A

hh:mm:ss HCPWRS2511A Spool files will be deleted because of COLD start.

hh:mm:ss HCPWRS2511A No files have been deleted yet.

hh:mm:ss HCPWRS2511A To continue COLD start and delete files, enter GO.

hh:mm:ss HCPWRS2511A To stop COLD start without deleting files, enter STOP.

go

The opportunity is given to stop the cold start and save your spool files. Since you do not need to save any spool files at this time, answer **go**.

IPL z/VM IIS

```
hh:mm:ss HCPWRS2512I Spooling initialization is complete.
hh:mm:ss DASD nnnn dump unit CP IPL pages nnnn
hh:mm:ss HCPAAU2700I System gateway ZVMV6R10 identified.
hh:mm:ss z/VM Version 6 Release 1.0, Service Level 0000 (64-bit),
built on IBM Virtualization Technology
hh:mm:ss There is no logmsg data
hh:mm:ss FILES: NO RDR, NO PRT, NO PUN
hh:mm:ss LOGON AT hh:mm:ss EDT DAY mm/dd/yy
hh:mm:ss GRAF nnnn LOGON AS OPERATOR USERS = n
hh:mm:ss HCPIOP952I nnnnM system storage
hh:mm:ss FILES: nnnnnnnn RDR, nnnnnnnn PRT, NO PUN
hh:mm:ss HCPCRC8082I Accounting records are accumulated for userid DISKACNT
```

5. Disconnect from the OPERATOR user ID.

```
disconnect
DISCONNECT AT hh:mm:ss {EST|EDT} weekday mm/dd/yy
```

Press enter or clear key to continue

ENTER

6. Log on as MAINT.

ENTER

The default password for MAINT is MAINT.

```
logon maint
```

```
z/VM Version 6 Release 1.0, Service Level 0000 (64-bit),
built on IBM Virtualization Technology
There is no logmsg data
FILES: NO RDR, NO PRT, NO PUN
LOGON AT hh:mm:ss EDT DAY mm/dd/yy
DMSIND2015W Unable to access the Y-disk. File mode Y (19E) not accessed
z/VM V6 R1.0 yyyy-mm-dd hh:mm
```

ENTER

```
DMSACP113S B(5E5) not attached or invalid device address
DMSACP113S D(51D) not attached or invalid device address
Ready; T=n.nn/n.nn hh:mm:ss
```

Message DMS113S is not a problem at this time.

Step 3. Run INSTPLAN

In this step, you will:

- Run INSTPLAN.

1. Run INSTPLAN.

instplan

**** NOW EXECUTING INSTPLAN EXEC ON *date* AT *time* ****

```

*** z/VM INSTALLATION PLANNING ***

Mark the product(s) selected to be installed into the VMSYS filepool with an
"F" and those selected to be installed to minidisks with an "M"

Install To  Product      Install To  Product      Install To  Product
-----
M           VM           M           OSA           M           PERFTK
M           VMHCD        M           RACF          M           DIRM
M           RSCS        M           ICKDSF        M           TCPIP

Place a nonblank character in front of the System Default Language you would
like for your system.

  _ AMENG      _ UCENG      _ KANJI

Place a nonblank character in front of the DASD model onto which your
z/VM system will be loaded. Only one model may be selected.

  _ 3390 Mod 3      _ 3390 Mod 9

PF1 = HELP  PF3/PF12 = QUIT  PF5 = Process  ENTER = Refresh

```

- See the installation worksheet (Table 1 on page 7) and enter:
 - “M” in the **Install To** column for each product you selected to be installed onto minidisks.
 - “F” in the **Install To** column for each product you selected to be installed into the VMSYS file pool.
- Place a nonblank character next to the system default language you selected for your system (see the installation worksheet, Table 1 on page 7).
- Place a nonblank character in front of the DASD model that matches *DASD type and model* recorded on the installation worksheet (Table 1 on page 7).
- Press F5 to process your selections.

Run INSTPLAN

Note: The output you see might vary depending on your planning choices.

F5

```
HCPPIX8475I THE PRODUCTS YOU SELECTED TO LOAD TO MINIDISK ARE:  
VM RSCS TCPIP OSA ICKDSF  
DIRM RACF PERFTK VMHCD
```

```
THE PRODUCTS YOU SELECTED TO LOAD TO SFS ARE:  
NONE
```

```
THE SYSTEM DEFAULT LANGUAGE SELECTED:  
AMENG
```

```
THE DASD TYPE YOU SELECTED TO LOAD ON IS:  
3390 model
```

```
THE DASD NEEDED TO LOAD z/VM ARE:  
610RES 610SPL 610PAG...
```

```
HCPINP8392I INSTPLAN EXEC ENDED SUCCESSFULLY  
Ready; T=n.nn/n.nn hh:mm:ss
```

Step 4. Run INSTVM

In this step, you will:

- Run INSTVM to build the directory for your system and load the items from the z/VM system DDR.

Note: Running the INSTVM requires a full screen terminal with at least 24 lines.

1. IPL CMS to verify the CMS saved system is available.

```

ip1 cms
DMSIND2015W Unable to access the Y-disk. File mode Y (19E) not accessed
z/VM V6.1.0   yyyy-mm-dd hh:mm
ENTER

DMSWSP100W Shared Y-STAT not available
DMSACP113S B(5E5) not attached or invalid device address
DMSACP113S D(51D) not attached or invalid device address
Ready; T=n.nn/n.nn hh:mm:ss

```

Note: If the CMS saved system does not exist, there is a problem with spool space. You must resolve the problem before continuing.

2. Select a free tape drive and mount the z/VM DDR tape. Attach the tape drive where the z/VM system DDR tape is mounted. The tape drive must be attached at address 181.

```

attach tapeaddr * 181
TAPE tapeaddr ATTACHED TO MAINT 181
Ready; T=n.nn/n.nn hh:mm:ss

```

tapeaddr
Real address of the tape drive.

3. Run INSTVM to install the z/VM system DDR.

```

instvm tape
**** NOW EXECUTING INSTVM EXEC ON date AT time ****
The minidisks with the END option specified in this directory will not be
included in the following DISKMAP file.

File USER DISKMAP A has been created.
CPRELEASE request for disk A scheduled.
HCPZAC6730I CPRELEASE request for disk A completed.
DASD 0CF1 DETACHED
CPACCESS request for mode A scheduled.
HCPZAC6732I CPACCESS request for MAINT's 0CF1 in mode A completed.
HCPIND8392I INSTDIR EXEC ENDED SUCCESSFULLY

z/VM USER DIRECTORY CREATION PROGRAM - VERSION 6 RELEASE 1.0
EOJ DIRECTORY UPDATED AND ON LINE
HCPDIR494I User directory occupies nn disk pages.
HCPWIN8381I CHECKING TAPE VOLUME NUMBER FOR DRIVE 181

```

Run INSTVM

Messages repeated for each disk restored (until total percent loaded reaches 100%)

```
HCPWIN8428I TOTAL PERCENT LOADED -> nn%
HCPWIN8380I RESTORING MINIDISK nnn TO valid
HCPDDR725D SOURCE DASD DEVICE WAS (IS) LARGER THAN OUTPUT DEVICE
RESTORING valid
DATA DUMPED mm/dd/yy AT hh.mm.ss GMT FROM valid RESTORED TO SCRATCH
INPUT CYLINDER EXTENTS      OUTPUT CYLINDER EXTENTS
  START      STOP      START      STOP
  nnnnnnnn   nnnnnnnn   nnnnnnnn   nnnnnnnn

END OF RESTORE
BYTES RESTORED nnnnnnnn
END OF JOB
```

```
HCPPLD8338I NOW EXECUTING ALLOCATION OF SYSTEM RESIDENCE PACK
HCPPLD8338I NOW EXECUTING UPDATE OF $MOVE$ $FILE$ C
HCPPLD8341I POSTLOAD FUNCTION "INSTALLATION CLEANUP" COMPLETED SUCCESSFULLY
HCPPLD8338I NOW EXECUTING DIRECTORY CLEANUP
HCPPLD8341I POSTLOAD FUNCTION "DIRECTORY CLEANUP AND ADD HELP DISK LINKS" COMPLETED SUCCESSFULLY
HCPPLD8338I NOW EXECUTING THE DIRECTXA COMMAND TO BRING THE UPDATED
HCPPLD8341I POSTLOAD FUNCTION "BRING UPDATED DIRECTORY ONLINE" COMPLETED SUCCESSFULLY
```

```
HCPPLD8392I POSTLOAD EXEC ENDED SUCCESSFULLY
DMSACC724I 2CC replaces C (2CC)
HCPIDV8493I ISSUING XAUTOLOG FOR VMSERVU
AUTO LOGON ***          VMSERVU  USERS = n
HCPCLS6056I XAUTOLOG information for VMSERVU: The IPL command is verified by the IPL
command processor.
VMSERVU : z/VM V6.1.0   yyyy-mm-dd hh:mm
VMSERVU : DMSACP723I B (193) R/O
VMSERVU : DMSWFV1117I FILESERV processing begun at hh:mm:ss on dd month yyyy
VMSERVU : DMSWFV1121I VMSERVU DMSPARMS A1 will be used for FILESERV processing
VMSERVU : DMSWFV1121I VMSYSU POOLDEF A1 will be used for FILESERV processing
VMSERVU : DMS5BB3045I Ready for operator communications
```

```
HCPIDV8493I ISSUING XAUTOLOG FOR VMSERVR
AUTO LOGON ***          VMSERVR  USERS = n
HCPCLS6056I XAUTOLOG information for VMSERVR: The IPL command is verified by the IPL
command processor.
VMSERVR : z/VM V6.1.0   yyyy-mm-dd hh:mm
VMSERVR : DMSACP723I B (193) R/O
VMSERVR : DMSWFV1117I FILESERV processing begun at hh:mm:ss on dd month yyyy
VMSERVR : DMSWFV1121I VMSERVR DMSPARMS A1 will be used for FILESERV processing
VMSERVR : DMSWFV1121I VMSYSR POOLDEF A1 will be used for FILESERV processing
VMSERVR : DMS6LG3335I CRR log recovery begins at mm-dd-yy hh:mm:ss
VMSERVR : DMS6LG3335I CRR log recovery completes at mm-dd-yy hh:mm:ss
VMSERVR : DMS5BB3045I Ready for operator communications
```

Extra messages received if all products were loaded to minidisks

```

DASD 0804 DETACHED
HCPIDV8493I ISSUING XAUTOLOG FOR VMSERVS
AUTO LOGON ***          VMSERVS  USERS = n
HCPCLS6056I XAUTOLOG information for VMSERVS: The IPL command is verified by the IPL
  command processor.
VMSERVS : z/VM V6.1.0   yyyy-mm-dd hh:mm
VMSERVS : DMSACP723I B (193) R/O
VMSERVS : DMSWV1117I FILESERV processing begun at hh:mm:ss on dd month yyyy
VMSERVS : DMSWV1121I VMSERVS DMSPARMS A1 will be used for FILESERV processing
VMSERVS : DMS4PD3400I Initializing begins for DDNAME = CONTROL
VMSERVS : DMS4PD3400I Initializing ends for DDNAME = CONTROL
VMSERVS : DMS4PD3400I Initializing begins for DDNAME = MDK00001
VMSERVS : DMS4PD3400I Initializing ends for DDNAME = MDK00001
VMSERVS : DMS4PD3400I Initializing begins for DDNAME = MDK00002
VMSERVS : DMS4PD3400I Initializing ends for DDNAME = MDK00002
VMSERVS : DMS4PD3400I Initializing begins for DDNAME = LOG1
VMSERVS : DMS4PD3400I Initializing ends for DDNAME = LOG1
VMSERVS : DMS4PD3400I Initializing begins for DDNAME = LOG2
VMSERVS : DMS4PD3400I Initializing ends for DDNAME = LOG2
VMSERVS : DMS5FD3032I File pool server has terminated
VMSERVS : DMSWV1120I File VMSYS POOLDEF A1 created or replaced
VMSERVS : DMSWV1117I FILESERV processing ended at hh:mm:ss on dd month yyyy
RDR FILE nnn SENT FROM VMSERVS  PUN WAS 0001 RECS 0004 CPY  001 A NOHOLD NOKEEP
VMSERVS : File FILESERV VALID A3 sent to MAINT at ZVMV6R10 on mm/dd/yy hh:mm:ss
VMSERVS : Ready; T=n.nn/n.nn hh:mm:ss

HCPQCS150A User VMSERVS has issued a VM read
VMSERVS : CONNECT= nn:nn:nn VIRTCPU= nnn:nn.nn TOTCPU= nnn:nn.nn
VMSERVS : LOGOFF AT hh:mm:ss timezone day mm/dd/yy BY MAINT
USER DSC  LOGOFF AS  VMSERVS  USERS = n      FORCED BY MAINT
DASD 0804 DETACHED

```

```

HCPIDV8493I ISSUING XAUTOLOG FOR VMSERVS
AUTO LOGON ***          VMSERVS  USERS = n

HCPCLS6056I XAUTOLOG information for VMSERVS: The IPL command is verified by the IPL
  command processor.
VMSERVS : z/VM V6.1.0   yyyy-mm-dd hh:mm
VMSERVS : DMSACP723I B (193) R/O
VMSERVS : DMSWV1117I FILESERV processing begun at hh:mm:ss on dd month yyyy
VMSERVS : DMSWV1121I VMSERVS DMSPARMS A1 will be used for FILESERV processing
VMSERVS : DMSWV1121I VMSYS POOLDEF A1 will be used for FILESERV processing
VMSERVS : DMS5BB3045I Ready for operator communications

```

You might not receive one or more of the following messages

```

HCPIDV8338I UPDATING SYSTEM TABLES AND CLEANING UP FILEPOOL DIRECTORIES
RC=0 from EXEC OPENVM UNMOUNT /
RC=0 from EXEC OPENVM UNMOUNT /
RC=0 from EXEC OPENVM UNMOUNT /
RC=0 from EXEC OPENVM UNMOUNT /
RC=0 from EXEC OPENVM UNMOUNT /

```

```

HCPIFP8392I INSTPOOL EXEC ENDED SUCCESSFULLY
HCPIVM8392I INSTVM EXEC ENDED SUCCESSFULLY
Ready; T=n.nn/n.nn hh:mm:ss

```

Run INSTVM

After this point, when you IPL the system, you should use the default IPL parameters and should no longer use COLD DRAIN NOAUTOLOG.

You are now finished with the z/VM system installation tape.

Step 5. Run SERVICE

In this step, you will:

- Run SERVICE to install the recommended service upgrade (RSU) and corrective service (COR).

1. Log on as MAINT.

```

ENTER
logon maint
:
Ready; T=n.nn/n.nn hh:mm:ss

```

The default password for MAINT is MAINT.

2. Make sure the file pool is available.

If you receive message DMS1153E, indicating the MAINT file pool is unavailable or unknown, you need to XAUTOLOG VMSESRVS, VMSESRVU, and VMSESRVR.

```

query limits all
Userid  Storage Group 4K Block Limit 4K Blocks Committed Threshold
userid1      2          n          n-nn%      nn%
userid2      2          n          n-nn%      nn%
:
Ready; T=n.nn/n.nn hh:mm:ss

```

3. Attach a tape drive and mount the RSU tape.

a. Attach a tape drive to MAINT as 181.

```

attach tapeaddr * 181
TAPE tapeaddr ATTACHED TO MAINT 181
Ready; T=n.nn/n.nn hh:mm:ss

```

b. Mount volume 1 of the RSU on the tape drive attached at address 181.

If the RSU has multiple volumes, either stack the RSU volumes on 181 or attach additional tape drives and mount each volume.

4. IPL CMS.

```

ipl cms
z/VM V6.1.0   yyyy-mm-dd hh:mm

```

```

ENTER
Ready; T=n.nn/n.nn hh:mm:ss

```

5. Run SERVICE.

a. If the volumes are mounted on 181, run SERVICE with no parameters.

```

service
VMFSRV2760I SERVICE processing started
:
VMFSRV2760I SERVICE processing completed
successfully
Ready; T=n.nn/n.nn hh:mm:ss

```

b. If the volumes are mounted on multiple tape drives, run SERVICE with the following parameters:

Run SERVICE

```

service all tapeaddr1 tapeaddr2 ...
VMFSRV2760I SERVICE processing started
:
VMFSRV2760I SERVICE processing completed
successfully
Ready; T=n.nn/n.nn hh:mm:ss

```

List the addresses of each tape volume.

tapeaddr1

Address of the tape drive where tape volume 1 is mounted.

tapeaddr2 ...

Address of the tape drive where tape volume 2 is mounted, and so on.

6. View the SERVICE messages log (VMFVIEW SERVICE) and handle any nonzero return codes. Base your actions on the following table:

If you received . . .	Then . . .
Return code 4	<ol style="list-style-type: none"> 1. Issue VMFVIEW SERVICE. 2. Ignore any warning messages listed in the note below. Take appropriate actions based on other warning messages you receive. 3. Go to "Step 6. Run PUT2PROD" on page 31.
A return code greater than 4	<ol style="list-style-type: none"> 1. Issue VMFVIEW SERVICE and check for warning and error messages. 2. Ignore any warning messages listed in the note below. Take appropriate actions based on other warning messages you receive. 3. Correct all errors reported in the error messages. 4. Restart by issuing the SERVICE command as displayed in the message VMFSRV2310W. 5. If you receive a nonzero return code, repeat substep 6. 6. Go to "Step 6. Run PUT2PROD" on page 31.

Note: You can ignore the following messages and their associated VMF1966W message.

- DMSLI0201W The following names are undefined: ISPLINK ARIPRDI
- DMSLI0201W The following names are undefined: DMSDSCSC
- DMSLI0201W The following names are undefined: DMSUSRX1 DMSUSRX2
- DMSLI0202W Duplicate identifier (Associated with object IOACMAIN MODULE.)
- DMSLKD004W Warning messages issued (Associated with objects ILBONBL, ILBONTR, ILBOREC, ILBORNT, ILBOSND, ILBOSNT, and ILBOSSN.)
- VMFSRV1221W The Stand Alone Dump Utility must be rebuilt.

7. Use the VMFUPDAT SYSMEMO command to review any memos that were received with this service.
8. If the PSP bucket contains COR service that should be applied at install, repeat "Step 5. Run SERVICE" on page 29 to install the service using COR in place of RSU.

Step 6. Run PUT2PROD

In this step, you will:

- Run PUT2PROD to place the product into production.

1. Log on as MAINT.

```

ENTER
logon maint
:
Ready; T=n.nn/n.nn hh:mm:ss

```

The default password for MAINT is MAINT.

2. Make sure the file pool is available.

If you receive message DMS1153E, indicating the MAINT file pool is unavailable or unknown, you need to XAUTOLOG VMSEVS, VMSERVU, and VMSERVR.

```

query limits all
Userid  Storage Group 4K Block Limit 4K Blocks Committed Threshold
userid1      2          n          n-nn%      nn%
userid2      2          n          n-nn%      nn%
:
Ready; T=n.nn/n.nn hh:mm:ss

```

3. IPL CMS and access the VMSES/E test build disk.

```

ipl cms
z/VM V6.1.0   yyyy-mm-dd hh:mm

```

```

ENTER
Ready; T=n.nn/n.nn hh:mm:ss

```

```

access 5E6 b
Ready;

```

4. Run PUT2PROD.

```

put2prod
VMFP2P2760I PUT2PROD processing started
:
VMFP2P2760I PUT2PROD processing completed successfully
Ready; T=n.nn/n.nn hh:mm:ss

```

5. Handle a nonzero return code. Base your action on the following table.

If you received . . .	Then . . .
Return code 4	<ol style="list-style-type: none"> Issue VMFVIEW PUT2PROD. Ignore any warning messages listed in the note below. Take appropriate actions based on other warning messages you receive.

Run PUT2PROD

If you received . . .	Then . . .
A return code greater than 4	<ol style="list-style-type: none"><li data-bbox="568 210 1427 241">1. Issue VMFVIEW PUT2PROD and check for warning and error messages.<li data-bbox="568 241 1427 315">2. Ignore any warning messages listed in the note below in this table. Take appropriate actions based on other warning messages you receive.<li data-bbox="568 315 1427 346">3. Correct all errors reported in the error messages.<li data-bbox="568 346 1427 378">4. Issue IPL CMS.<li data-bbox="568 378 1427 409">5. Issue PUT2PROD.<li data-bbox="568 409 1427 472">6. If you receive a nonzero return code, repeat substep 5 on page 31.

Note: You can ignore the following messages.

- DMSDCS1083E Saved segment \$\$DMY\$\$ does not exist
- DMSWLG292W Text data will be loaded at '20000'x in user area; user data may be overwritten.
- DTCPRD3043W File *fn ft fm* has been updated; It's contents should be reviewed for changes that may affect your use of this file.
- TCPMSM0002W File TCPIP DATA cannot be located
- TCPMSM0002W TCP/IP appears not to have been configured

Step 7. Shut Down and Re-IPL the System

In this step, you will:

- Shut down the V6.1 system.
- IPL the V6.1 system using the new CP nucleus.

1. Shut down and re-IPL the V6.1 system.

shutdown reipl

```
SYSTEM SHUTDOWN STARTED
Ready; T=n.nn/n.nn hh:mm:ss
```

The shut down message is displayed on all enabled consoles.

The real system console shows a disabled PSW wait state.

```
HCPWRP963I STARTING SHUTDOWN STEP . . .
:
:
HCPWRP962I VM SHUTDOWN COMPLETED IN nn SEC
HCPWRP9277I SYSTEM TERMINATION COMPLETE,
      ATTEMPTING RESTART
```

HCP963I, HCP962I, and HCP9277I will appear on the operator's console.

```
hh:mm:ss HCPWRP9277I SYSTEM TERMINATION COMPLETE.
      ATTEMPTING RESTART
hh:mm:ss z/VM SYSTEM RESTART FROM SHUTDOWN REIPL
hh:mm:ss z/VM V6 R1.0
      SERVICE LEVEL nnnn (64-BIT)
```

```
hh:mm:ss SYSTEM NUCLEUS CREATED ON yyyy-mm-dd AT hh:mm:ss,
      LOADED FROM 610RES
```

```
hh:mm:ss *****
hh:mm:ss * LICENSED MATERIALS - PROPERTY OF IBM* *
hh:mm:ss * 5741-A07 (C) COPYRIGHT IBM CORP. 1983, *
hh:mm:ss * 2009. ALL RIGHTS RESERVED. *
hh:mm:ss * US GOVERNMENT USERS RESTRICTED RIGHTS - *
hh:mm:ss * USE, DUPLICATION OR DISCLOSURE *
hh:mm:ss * RESTRICTED BY GSA ADP SCHEDULE CONTRACT *
hh:mm:ss * WITH IBM CORP. *
hh:mm:ss * *
hh:mm:ss * * TRADEMARK OF INTERNATIONAL BUSINESS *
hh:mm:ss * * MACHINES *
hh:mm:ss *****
```

```
hh:mm:ss HCPZC06718I Using parm disk 1 on volume valid (device xxxx).
hh:mm:ss HCPZC06718I Parm disk resides on cylinders xx through xx.
```

Attention: If you receive informational message HCPIIS954I, you have duplicate DASD with the same label and *must correct* this error before continuing.

```
hh:mm:ss The directory on volume 610RES at address nnnn
      has been brought online.
```

```
hh:mm:ss HCPWRS2513I
hh:mm:ss HCPWRS2513I Spool files available {nnnn|none}
hh:mm:ss HCPWRS2512I Spooling initialization is complete.
```

```
hh:mm:ss FILES: nnn RDR, nnn PRT, nnn PUN
hh:mm:ss LOGON AT hh:mm:ss {EST|EDT} weekday mm/dd/yy
:
```

```
hh:mm:ss HCPIOP952I nnnnM system storage
hh:mm:ss FILES: nnnnnn RDR, nnnnnn PRT, NO PUN
```

Shut Down and Re-IPL the System

Message HCP952I tells you the amount of storage available.

The FILES message refers to operator spool files.

CP automatically disconnects from the primary system operator user ID (OPERATOR).

```
hh:mm:ss HCPUS0967I Disconnect OPERATOR - system
          restarted SHUTDOWN and system console
          not VM operator console
hh:mm:ss HCPCRC8082I Accounting records are accumulating for userid DISKACNT
hh:mm:ss DISCONNECT AT hh:mm:ss {EST|EDT} weekday mm/dd/yy
hh:mm:ss Press enter or clear key to continue
```

ENTER

Press Enter or Clear to continue.

2. Log on as MAINT.

```
logon maint
:
Ready; T=n.nn/n.nn hh:mm:ss
```

The password for MAINT is MAINT.

What to do next

See Part 3, "Post z/VM System Installation," on page 129.

Chapter 3. Second-Level DDR Installation Method

In this chapter, you will:

Use step-by-step procedures to install the z/VM system DDR second-level on an existing z/VM system.

Step 1. Load the Installation Tools from the z/VM System DDR

In this step, you will

- Log on to a first-level user ID.
- Mount the z/VM system DDR tape.
- Load the installation tools.

1. Before you begin, fill out the installation worksheet (Table 1 on page 7) in Chapter 1, “Plan Your DDR Installation.”
2. From your current operating system, log on to the first-level user ID that you will use to install z/VM version 6 release 1. This user ID must meet the following requirements:
 - 64 MB virtual storage.
 - Privilege classes B and G.
 - Write access to a 191 minidisk with at least 500 4-KB blocks of available space. A shared file system directory cannot be used.
 - To change installation pack labels, the installation user ID must be able to issue the DEFINE MDISK command. The IBM default privilege class for this command is class A. The DEFINE MDISK command also requires the user ID to have DEVMAINT on the OPTION directory statement in its directory entry.
 - You must IPL the z/VM IIS (“Step 4. IPL z/VM IIS” on page 42) on the same user ID you used to run INSTPLAN and INSTIIS.
3. Verify you have both the installation tape and the latest RSU tape(s).
 - If the RSU (or COR) service is electronic or on CD-ROM you need to receive the service files to a minidisk attached to your installation user ID on your first-level system *before* IPLing your second-level system. Follow the instructions included with the electronic or CD-ROM service files to receive and restore the service files to a minidisk that can be temporarily attached to your second-level system.

Note: You must preserve the file attribute of FIXED BINARY 1024 through all intermediary transports.

4. Access your 191 minidisk as A. It must be 191 and it must be a minidisk, not an SFS directory. The installation tools will be loaded to the A disk. Files are created on this disk that are accessed by installation execs in a later step. Verify there are at least 500 4-KB blocks of space available (BLKS LEFT).

```
access 191 a
Ready; T=n.nn/n.nn hh:mm:ss
```

```
query disk a
LABEL  VDEV  M  STAT  CYL  TYPE  BLKSZ  FILES  BLKS  USED-(%)  BLKS  LEFT  BLK  TOTAL
1b1191  191   A  R/W   nn  3390  4096   nnn   nnnn-nn   500   nnnn
```

```
Ready;
```

5. Choose the address of your tape drive. A tape drive is needed for one volume.
To display all available tape drives on your system, enter:

```
query tape free
```

6. Attach an available tape drive as 181.

```
attach tapeaddr * 181  
TAPE tapeaddr ATTACHED TO userID 181  
Ready; T=n.nn/n.nn hh:mm:ss
```

tapeaddr

Address of the tape drive where the z/VM system DDR tape will be mounted.

userID

First-level user ID you logged on to in substep 2 on page 36.

7. Mount the z/VM system DDR tape on the tape drive attached as 181.
8. Load the installation tools from the z/VM system DDR to your (191) A-disk.

```
rewind 181  
Ready; T=n.nn/n.nn hh:mm:ss
```

```
vmfplc2 fsf 4  
Ready; T=n.nn/n.nn hh:mm:ss
```

```
vmfplc2 load * * a  
Loading ...  
:  
End-of-file or end-of-tape  
Ready; T=n.nn/n.nn hh:mm:ss
```

```
rew 181  
Ready; T=n.nn/n.nn hh:mm:ss
```

Step 2. Run INSTPLAN

In this step, you will:

- Run INSTPLAN.

1. Run INSTPLAN.

```
instplan
```

```
**** NOW EXECUTING INSTPLAN EXEC ON date AT time ****
```

```
*** z/VM INSTALLATION PLANNING ***
```

Mark the product(s) selected to be installed into the VMSYS filepool with an "F" and those selected to be installed to minidisks with an "M"

Install To	Product	Install To	Product	Install To	Product
M	VM	M	OSA	M	PERFTK
M	VMHCD	M	RACF	M	DIRM
M	RSCS	M	ICKDSF	M	TCPIP

Place a nonblank character in front of the System Default Language you would like for your system.

```
_ AMENG      _ UCENG      _ KANJI
```

Place a nonblank character in front of the DASD model onto which your z/VM system will be loaded. Only one model may be selected.

```
_ 3390 Mod 3      _ 3390 Mod 9
```

```
PF1 = HELP  PF3/PF12 = QUIT  PF5 = Process  ENTER = Refresh
```

Figure 2. Installation Planning Panel

- See the installation worksheet (Table 1 on page 7) and enter:
 - "M" in the **Install To** column for each product you selected to be installed onto minidisks.
 - "F" in the **Install To** column for each product you selected to be installed into the VMSYS file pool.
- Place a nonblank character next to the *System Default Language* you selected for your system in the installation worksheet (Table 1 on page 7).
- Place a nonblank character in front of the DASD model that matches the *DASD type and model* recorded on the installation worksheet (Table 1 on page 7).
- Press F5 to process your selections.

Note: The output you see may be different due to your planning choices.

F5

```
HCPPIX8475I THE PRODUCTS YOU SELECTED TO LOAD TO MINIDISK ARE:  
VM RSCS TCPIP OSA ICKDSF  
DIRM RACF PERFTK VMHCD
```

```
THE PRODUCTS YOU SELECTED TO LOAD TO SFS ARE:  
NONE
```

```
THE SYSTEM DEFAULT LANGUAGE SELECTED:  
AMENG
```

```
THE DASD TYPE YOU SELECTED TO LOAD ON IS:  
3390 model
```

```
THE DASD NEEDED TO LOAD z/VM ARE:  
610RES 610SPL 610PAG...
```

```
HCPINP8392I INSTPLAN EXEC ENDED SUCCESSFULLY  
Ready; T=n.nn/n.nn hh:mm:ss
```

Restore the Initial Installation System (IIS)

Step 3. Restore the Initial Installation System (IIS)

In this step, you will:

- Format the DASD.
- Load IIS from the z/VM system DDR.

1. See the installation worksheet (Table 1 on page 7). Attach all the DASD listed in the worksheet that are not already attached. Enter the following ATTACH command for each DASD:

```
attach dasdaddr *
DASD dasdaddr ATTACHED TO userID dasdaddr
      ⋮
Ready; T=n.nn/n.nn hh:mm:ss
```

dasdaddr
Address of the DASD.

userID
First-level user ID logged on to previously.

Attention: Issue the QUERY DASD ATTACH * command to verify there are no DASD attached to your user ID with the same label as those being used for installation. You must detach any duplicate-labeled DASD from your user ID to prevent bringing them online.

2. Run INSTIIS to format and label your installation DASD and to restore the IIS.

instiis

```
*** z/VM INSTALLATION DASD FORMAT/RESTORE ***
```

PACK TYPE	DASD LABEL	DASD ADDRESS	VIRTUAL TAPE ADDRESS	DO NOT FORMAT DASD
RES	610RES	_____	_____	_____
SPOOL	610SPL	_____		
PAGE	610PAG	_____		
USER	610W01	_____		
USER	610W02	_____		
USER	610W03	_____		

PF1 = HELP PF3/PF12 = QUIT PF5 = Process ENTER = Refresh

Figure 3. Installation DASD Format and Restore Panel (3390 Model Layout)

- a. If you want to change the labels of the SPOOL, PAGE, or USER DASD, fill in the DASD LABEL field with the new labels. You cannot change the 610RES label. To use the function to change the installation DASD labels, the user ID must be able to issue the DEFINE MDISK command. The IBM default privilege class for this command is class A. The DEFINE MDISK command also requires the user ID to have DEVMAINT on its OPTION directory statement.
- b. Fill in the DASD addresses using the information from the installation worksheet (Table 1 on page 7). For more information and help, press F1.
- c. Fill in the tape address (181) where z/VM system DDR tape is mounted.

Restore the Initial Installation System (IIS)

- d. Place a nonblank character in the DO NOT FORMAT DASD column only if you have already CP formatted your DASD for this installation using ICKDSF or CPFMTXA. The DASD will be labeled, but not formatted.
- e. Press F5 to process.

F5

```
HCPIIX8381I CHECKING TAPE VOLUME NUMBER FOR DRIVE 181
HCPIIX8377R YOU HAVE SELECTED TO FORMAT THE FOLLOWING DASD:
HCPIIX8483R YOU HAVE SELECTED NOT TO FORMAT YOUR DASD.
              THIS ASSUMES YOU HAVE ALREADY FORMATTED THE
              DASD AND THIS EXEC WILL ONLY RELABEL AS
              FOLLOWS
```

Depending on whether you chose to format your DASD, you will receive either message HCPIIX8377R or HCPIIX8483R.

```
610RES dasdaddr
lblspl dasdaddr
lblpag dasdaddr
lblw01 dasdaddr
lblw02 dasdaddr
lblw03 dasdaddr
```

```
DO YOU WANT TO CONTINUE ? (Y|N)
y
```

```
HCPIIX8490I NOW FORMATTING LABELING DASD dasdaddr
HCPIIX8490I NOW FORMATTING LABELING DASD dasdaddr
HCPIIX8490I NOW FORMATTING LABELING DASD dasdaddr
:
HCPIIX8380I RESTORING IIS TO 610RES and lblspl
```

```
RESTORING 610RES
DATA DUMPED mm/dd/yy AT hh.mm.ss GMT FROM 610RES RESTORED TO 610RES
INPUT CYLINDER EXTENTS          OUTPUT CYLINDER EXTENTS
  START      STOP                START      STOP
    0         158                  0         158
  399        685                  399        685
```

```
END OF RESTORE
BYTES RESTORED nnnnnnnnnn
```

```
HCPDDR717D DATA DUMPED FROM 610SPL
TO BE RESTORED TO spllabel
```

You will receive this message if you changed the label for the 610SPL pack.

```
RESTORING 610SPL
DATA DUMPED mm/dd/yy AT hh.mm.ss GMT FROM 610SPL RESTORED TO lblspl
INPUT CYLINDER EXTENTS          OUTPUT CYLINDER EXTENTS
  START      STOP                START      STOP
    0         199                  0         199
  END OF RESTORE
BYTES RESTORED nnnnnnnnnn
```

```
END OF JOB
HCPIIX8490I NOW ALLOCATING DASD dasdaddr (RES PACK)
HCPIIX8490I NOW ALLOCATING DASD dasdaddr (SPOOLING)
HCPIIX8490I NOW ALLOCATING DASD dasdaddr (PAGING)
HCPINI8392I INSTIIS EXEC ENDED SUCCESSFULLY
Ready; T=n.nn/n.nn hh:mm:ss
```

Step 4. IPL z/VM IIS

In this step, you will:

- IPL the z/VM IIS.

Note: You must IPL the z/VM IIS on the same user ID you used to run INSTPLAN and INSTIIS.

1. Reset your virtual machine and make sure the z/VM system will recognize your terminal as a 3277, 3278, or 3279.

```
system clear
Storage cleared - system reset.
```

```
terminal conmode 3270
```

2. Verify you have 64 MB of virtual storage. If you have less than 64 MB of virtual storage, issue the DEFINE command to set your virtual storage to 64 MB.

```
query virtual storage
STORAGE = nnnnM
```

```
define storage 64M
STORAGE = 64M
Storage cleared - system reset
```

3. Set the virtual machine mode to ESA.

```
set machine esa
```

4. Query the console to determine the virtual console address (*consaddr*). This address is required in the next substep.

```
query console
CONS consaddr ON LDEV nnnn TERM START
consaddr CL T NOCONT NOHOLD COPY 001 READY FORM STDN
consaddr TO userid dev DIST nnnn FLASHC 000 DEST OFF
consaddr FLASH CHAR MDFY 0 FCB LPP OFF
consaddr 3270 NOEOF OPEN nnnn NOKEEP NOMSG NONAME
consaddr SUBCHANNEL = nnnn
```

5. IPL the IIS you loaded to the system residence device (610RES).

```
ipl dasdaddr clear loadparm consaddr
```

```
dasdaddr
Address of the system residence device
(610RES).
```

```
consaddr
Virtual console address determined in substep 4.
```

The Stand Alone Program Loader panel displays after issuing the IPL command.

```

STAND ALONE PROGRAM LOADER: z/VM VERSION 6 RELEASE 1.0

DEVICE NUMBER:  dasdaddr  MINIDISK OFFSET:  nnnnnnnn  EXTENT:  1
MODULE NAME:     CPLOAD    LOAD ORIGIN:      1000

-----IPL PARAMETERS-----
cons=consaddr

-----COMMENTS-----

-----

9= FILELIST  10= LOAD  11= TOGGLE EXTENT/OFFSET

```

Figure 4. Sample Stand Alone Program Loader Panel

6. Move the cursor to the IPL PARAMETERS field and type

```
cons=consaddr
```

```
consaddr
```

Virtual console address determined in substep 4 on page 42. Spaces are not allowed around the equal sign.

7. Press F10 to load.

F10

```

hh:mm:ss z/VM V6 R1.0 SERVICE LEVEL 0000 (64-BIT)

hh:mm:ss SYSTEM NUCLEUS CREATED ON yyyy-mm-dd AT hh:mm:ss,
         LOADED FROM 610RES
hh:mm:ss *****
hh:mm:ss * LICENSED MATERIALS - PROPERTY OF IBM* *
hh:mm:ss * 5741-A07 (C) COPYRIGHT IBM CORP. 1983, *
hh:mm:ss * 2009. ALL RIGHTS RESERVED. *
hh:mm:ss * US GOVERNMENT USERS RESTRICTED RIGHTS - *
hh:mm:ss * USE, DUPLICATION OR DISCLOSURE *
hh:mm:ss * RESTRICTED BY GSA ADP SCHEDULE CONTRACT *
hh:mm:ss * WITH IBM CORP. *
hh:mm:ss * *
hh:mm:ss * * TRADEMARK OF INTERNATIONAL BUSINESS *
hh:mm:ss * MACHINES *
hh:mm:ss *****

hh:mm:ss HCPZC06718I Using parm disk 1 on volume 610RES (device nnnn).
hh:mm:ss HCPZC06718I Parm disk resides on cylinders nnn through nnn.
:

```

You might receive an informational message, HCPISU951I, about volumes not mounted. If you are not using those volume labels, ignore this message.

Note: If you receive informational message HCPIIS954I, you have duplicate volumes with the same label. You must return to the first-level CP environment by entering SHUTDOWN at the next prompt. Detach the duplicate volumes and then go back to substep 1 on page 42.

IPL z/VM IIS

```
hh:mm:ss Start ((Warm|Force|COLD|CLEAN) (DRain)
              (DISable) (NODIRect) (NOAUTOlog)) or (SHUTDOWN)
cold drain noauto log
```

Because there is no data or accounting information to recover, use COLD DRAIN to request a cold start. Use NOAUTOLOG at this point because you cannot have the servers and all user IDs logged on.

```
NOW hh:mm:ss {EST|EDT} weekday yyy-mm-dd
Change TOD clock (yes|no)
no
```

CP logs on the primary system operator user ID (OPERATOR).

```
hh:mm:ss The directory on volume 610RES at address nnnn
          has been brought online.
```

```
hh:mm:ss HCPWRS2513I
```

```
hh:mm:ss HCPWRS2513I Spool files available nnnn
```

Note: Depending on the type of spool files available, you might receive the following prompt:

Spool Files Prompt

```
hh:mm:ss HCPWRS2513I
hh:mm:ss HCPWRS2513I Spool files on offline volumes      {nnnn|NONE}
hh:mm:ss HCPWRS2513I Spool files with I/O errors       {nnnn|NONE}
hh:mm:ss HCPWRS2513I Spool files with control errors   {nnnn|NONE}
hh:mm:ss HCPWRS2513I Spool files to be discarded       {nnnn|NONE}
hh:mm:ss HCPWRS2513I                                     -----
hh:mm:ss HCPWRS2513I Total files to be deleted         nnnn
hh:mm:ss HCPWRS2511A
hh:mm:ss HCPWRS2511A Spool files will be deleted because of
                    COLD start.
hh:mm:ss HCPWRS2511A No files have been deleted yet.

hh:mm:ss HCPWRS2511A To continue COLD start and delete files,
                    enter GO.
hh:mm:ss HCPWRS2511A To stop COLD start without deleting
                    files, enter STOP.
```

go

The system gives you an opportunity to stop the cold start and save your spool files. You do not need to save any spool files at this time; answer **go**.

```
hh:mm:ss HCPWRS2512I Spooling initialization is complete.
hh:mm:ss DASD nnnn dump unit CP IPL pages nnnn
hh:mm:ss HCPAAU2700I System gateway ZVMV6R10 identified.
hh:mm:ss z/VM Version 6 Release 1.0, Service Level 0000 (64-bit),
built on IBM Virtualization Technology
hh:mm:ss There is no logmsg data
hh:mm:ss FILES: NO RDR, NO PRT, NO PUN
hh:mm:ss LOGON AT hh:mm:ss EDT DAY mm/dd/yy
hh:mm:ss GRAF nnnn LOGON AS OPERATOR USERS = n
hh:mm:ss HCPIOP952I nnnnM system storage
hh:mm:ss FILES: nnnnnnnn RDR, nnnnnnnn PRT, NO PUN
hh:mm:ss HCPCRC8082I Accounting records are accumulating for userid DISKACNT
```

8. Disconnect from the OPERATOR user ID.

```
disconnect
DISCONNECT AT hh:mm:ss {EST|EDT} weekday mm/dd/yy
```

Press enter or clear key to continue

ENTER

9. Log on as MAINT.

ENTER

The default password for MAINT is MAINT.

logon maint

```
z/VM Version 6 Release 1.0, Service Level 0000 (64-bit),
built on IBM Virtualization Technology
There is no logmsg data
FILES: nnnn RDR, NO PRT, NO PUN
LOGON AT hh:mm:ss EDT DAY mm/dd/yy
DMSIND2015W Unable to access the Y-disk. File mode Y (19E) not accessed
z/VM V6.1.0   yyyy-mm-dd hh:mm
```

ENTER

```
DMSACP113S B(5E5) not attached or invalid device address
DMSACP113S D(51D) not attached or invalid device address
```

Message DMSACP113S is not a problem at this time.

Ready; T=n.nn/n.nn hh:mm:ss

Step 5. Run INSTVM

In this step, you will:

- Run INSTVM to build the directory for your system and load the items from the z/VM system DDR.

Note: Running the INSTVM requires a full screen terminal with at least 24 lines.

1. IPL CMS to verify the CMS saved system is available.

```
ipl cms
DMSIND2015W Unable to access the Y-disk. File mode Y (19E) not accessed
z/VM V6.1.0   yyyy-mm-dd hh:mm
ENTER

DMSWSP100W Shared Y-STAT not available
DMSACP113S B(5E5) not attached or invalid device address
DMSACP113S D(51D) not attached or invalid device address
Ready; T=n.nn/n.nn hh:mm:ss
```

Note: If the CMS saved system does not exist, there is a problem with spool space. You must resolve the problem before continuing.

2. Attach the tape drive on which the z/VM system DDR tape is mounted to your second-level system at address 181. The tape drive was previously attached to your first-level user ID at address 181.

```
attach 181 * 181
TAPE 181 ATTACHED TO MAINT 181
Ready; T=n.nn/n.nn hh:mm:ss
```

3. If the z/VM system DDR tape is not already mounted, mount the tape on the drive.

4. Run INSTVM to install the z/VM system DDR.

```
instvm tape
**** NOW EXECUTING INSTVM EXEC ON date AT time ****
DASD 0199 DETACHED
The minidisks with the END option specified in this directory will not be
included in the following DISKMAP file.

File USER DISKMAP A has been created.
CPRELEASE request for disk A scheduled.
HCPZAC6730I CPRELEASE request for disk A completed.
DASD 0CF1 DETACHED
CPACCESS request for mode A scheduled.
HCPZAC6732I CPACCESS request for MAINT's 0CF1 in mode A completed.
HCPIND8392I INSTDIR EXEC ENDED SUCCESSFULLY

z/VM USER DIRECTORY CREATION PROGRAM - VERSION 6 RELEASE 1.0
EOJ DIRECTORY UPDATED AND ON LINE
HCPDIR494I User directory occupies nn disk pages.
HCPWIN8381I CHECKING TAPE VOLUME NUMBER FOR DRIVE 181
```


Messages repeated for each disk restored (until total percent loaded reaches 100%)

```
HCPWIN8428I TOTAL PERCENT LOADED -> nn%
HCPWIN8380I RESTORING MINIDISK nnn TO valid
HCPDDR725D SOURCE DASD DEVICE WAS (IS) LARGER THAN OUTPUT DEVICE
RESTORING valid
DATA DUMPED mm/dd/yy AT hh.mm.ss GMT FROM valid RESTORED TO SCRATCH
INPUT CYLINDER EXTENTS      OUTPUT CYLINDER EXTENTS
  START      STOP      START      STOP
  nnnnnnnn   nnnnnnnn   nnnnnnnn   nnnnnnnn

END OF RESTORE
BYTES RESTORED nnnnnnnn
END OF JOB
```

```
HCPPLD8338I NOW EXECUTING ALLOCATION OF SYSTEM RESIDENCE PACK
HCPPLD8338I NOW EXECUTING UPDATE OF $MOVE$ $FILE$ C
HCPPLD8341I POSTLOAD FUNCTION "INSTALLATION CLEANUP" COMPLETED SUCCESSFULLY
HCPPLD8338I NOW EXECUTING DIRECTORY CLEANUP
HCPPLD8341I POSTLOAD FUNCTION "DIRECTORY CLEANUP AND ADD HELP DISK LINKS" COMPLETED SUCCESSFULLY
HCPPLD8338I NOW EXECUTING THE DIRECTXA COMMAND TO BRING THE UPDATED USER DIRECTORY ONLINE
HCPPLD8341I POSTLOAD FUNCTION "BRING UPDATED DIRECTORY ONLINE" COMPLETED SUCCESSFULLY
```

```
HCPPLD8392I POSTLOAD EXEC ENDED SUCCESSFULLY
DMSACC724I 2CC replaces C (2CC)
HCPIDV8493I ISSUING XAUTOLOG FOR VMSERVU
AUTO LOGON ***          VMSERVU  USERS = n
HCPCLS6056I XAUTOLOG information for VMSERVU: The IPL command is verified by the IPL
command processor.
VMSERVU : z/VM V6.1.0   yyyy-mm-dd hh:mm
VMSERVU : DMSACP723I B (193) R/O
VMSERVU : DMSWV1117I FILESERV processing begun at hh:mm:ss on dd month yyyy
VMSERVU : DMSWV1121I VMSERVU DMSPARMS A1 will be used for FILESERV processing
VMSERVU : DMSWV1121I VMSYSU POOLDEF A1 will be used for FILESERV processing
VMSERVU : DMS5BB3045I Ready for operator communications
```

```
HCPIDV8493I ISSUING XAUTOLOG FOR VMSERVR
AUTO LOGON ***          VMSERVR  USERS = n
HCPCLS6056I XAUTOLOG information for VMSERVR: The IPL command is verified by the IPL
command processor.
VMSERVR : z/VM V6.1.0   yyyy-mm-dd hh:mm
VMSERVR : DMSACP723I B (193) R/O
VMSERVR : DMSWV1117I FILESERV processing begun at hh:mm:ss on dd month yyyy
VMSERVR : DMSWV1121I VMSERVR DMSPARMS A1 will be used for FILESERV processing
VMSERVR : DMSWV1121I VMSYSR POOLDEF A1 will be used for FILESERV processing
VMSERVR : DMS6LG3335I CRR log recovery begins at mm-dd-yy hh:mm:ss
VMSERVR : DMS6LG3335I CRR log recovery completes at mm-dd-yy hh:mm:ss
VMSERVR : DMS5BB3045I Ready for operator communications
```

Run INSTVM

Extra messages received if all products were loaded to minidisks

```
DASD 0804 DETACHED
HCPIDV8493I ISSUING XAUTOLOG FOR VMSERVS
AUTO LOGON ***          VMSERVS  USERS = n
HCPCLS6056I XAUTOLOG information for VMSERVS: The IPL command is verified by the IPL
command processor.
VMSERVS : z/VM V6.1.0    yyyy-mm-dd hh:mm
VMSERVS : DMSACP723I B (193) R/O
VMSERVS : DMSWV1117I FILESERV processing begun at hh:mm:ss on dd month yyyy
VMSERVS : DMSWV1121I VMSERVS DMSPARMS A1 will be used for FILESERV processing
VMSERVS : DMS4PD3400I Initializing begins for DDNAME = CONTROL
VMSERVS : DMS4PD3400I Initializing ends for DDNAME = CONTROL
VMSERVS : DMS4PD3400I Initializing begins for DDNAME = MDK00001
VMSERVS : DMS4PD3400I Initializing ends for DDNAME = MDK00001
VMSERVS : DMS4PD3400I Initializing begins for DDNAME = MDK00002
VMSERVS : DMS4PD3400I Initializing ends for DDNAME = MDK00002
VMSERVS : DMS4PD3400I Initializing begins for DDNAME = LOG1
VMSERVS : DMS4PD3400I Initializing ends for DDNAME = LOG1
VMSERVS : DMS4PD3400I Initializing begins for DDNAME = LOG2
VMSERVS : DMS4PD3400I Initializing ends for DDNAME = LOG2
VMSERVS : DMS5FD3032I File pool server has terminated
VMSERVS : DMSWV1120I File VMSYS POOLDEF A1 created or replaced
VMSERVS : DMSWV1117I FILESERV processing ended at hh:mm:ss on dd month yyyy
RDR FILE nnnn SENT FROM VMSERVS  PUN WAS 0001 RECS 0004 CPY  001 A NOHOLD NOKEEP
VMSERVS : File FILESERV VALID A3 sent to MAINT at ZVMV6R10 on mm/dd/yy hh:mm:ss
VMSERVS : Ready; T=n.nn/n.nn hh:mm:ss

HCPQCS150A User VMSERVS has issued a VM read
VMSERVS : CONNECT= nn:nn:nn VIRTCPU= nnn:nn.nn TOTCPU= nnn:nn.nn
VMSERVS : LOGOFF AT hh:mm:ss timezone day mm/dd/yy BY MAINT
USER DSC  LOGOFF AS  VMSERVS  USERS = n      FORCED BY MAINT
DASD 0804 DETACHED
```

```
HCPIDV8493I ISSUING XAUTOLOG FOR VMSERVS
AUTO LOGON ***          VMSERVS  USERS = n

HCPCLS6056I XAUTOLOG information for VMSERVS: The IPL command is verified by the IPL
command processor.
VMSERVS : z/VM V6.1.0    yyyy-mm-dd hh:mm
VMSERVS : DMSACP723I B (193) R/O
VMSERVS : DMSWV1117I FILESERV processing begun at hh:mm:ss on dd month yyyy
VMSERVS : DMSWV1121I VMSERVS DMSPARMS A1 will be used for FILESERV processing
VMSERVS : DMSWV1121I VMSYS POOLDEF A1 will be used for FILESERV processing
VMSERVS : DMS5BB3045I Ready for operator communications
```

You might not receive one or more of the following messages

```
HCPIDV8338I UPDATING SYSTEM TABLES AND CLEANING UP FILEPOOL DIRECTORIES
RC=0 from EXEC OPENVM UNMOUNT /
RC=0 from EXEC OPENVM UNMOUNT /
RC=0 from EXEC OPENVM UNMOUNT /
RC=0 from EXEC OPENVM UNMOUNT /
RC=0 from EXEC OPENVM UNMOUNT /
```

```
HCPIFP8392I INSTPOOL EXEC ENDED SUCCESSFULLY
HCPIVM8392I INSTVM EXEC ENDED SUCCESSFULLY
Ready; T=n.nn/n.nn hh:mm:ss
```

After this point, when you IPL the system, you should use the default IPL parameters and should no longer use COLD DRAIN NOAUTOLOG.

You are now finished with the z/VM system installation tape.

Step 6. Run SERVICE

In this step, you will:

- Run SERVICE to install the recommended service upgrade (RSU) and corrective service (COR).

1. Log on as MAINT.

ENTER

logon maint

⋮

Ready; T=n.nn/n.nn hh:mm:ss

The default password for MAINT is MAINT.

2. Make sure the file pool is available.

If you receive message DMS1153E, indicating the MAINT file pool is unavailable or unknown, you need to XAUTOLOG VMSESRVS, VMSESRVU, and VMSESRVR.

query limits all

Userid	Storage Group	4K Block Limit	4K Blocks Committed	Threshold
userid1	2	n	n-nn%	nn%
userid2	2	n	n-nn%	nn%

⋮

Ready; T=n.nn/n.nn hh:mm:ss

3. If the RSU is not on tape, skip to substep 4 on page 51. Otherwise, apply the RSU service from tape.

a. Attach a tape drive to MAINT as 181.

attach tapeaddr * 181

TAPE tapeaddr ATTACHED TO MAINT 181

Ready; T=n.nn/n.nn hh:mm:ss

b. Mount volume 1 of the RSU on the tape drive attached at address 181.

If the RSU has multiple volumes, either stack the RSU volumes on 181 or attach additional tape drives and mount each volume.

c. IPL CMS.

ipl cms

z/VM V6.1.0 yyyy-mm-dd hh:mm

ENTER

Ready; T=n.nn/n.nn hh:mm:ss

d. If the volumes are mounted on 181, run SERVICE with no parameters.

service

VMFSRV2760I SERVICE processing started

⋮

VMFSRV2760I SERVICE processing completed

successfully

Ready; T=n.nn/n.nn hh:mm:ss

e. If the volumes are mounted on multiple tape drives, run SERVICE with the following parameters:

```

service all tapeaddr1 tapeaddr2 ...
VMFSRV2760I SERVICE processing started
:
VMFSRV2760I SERVICE processing completed
successfully
Ready; T=n.nn/n.nn hh:mm:ss

```

List the addresses of each tape volume.

```

tapeaddr1
  Address of the tape drive where tape volume 1
  is mounted.
tapeaddr2 ...
  Address of the tape drive where tape volume 2
  is mounted, and so on.

```

4. If the RSU is not electronic or on CD-ROM, skip to substep 5 on page 52. Otherwise, apply the electronic or CD-ROM RSU service.

- a. Attach and access the minidisk containing the service files to the MAINT user ID on your second-level system.

Requirement: The service files must be already loaded to minidisk *diskaddr*, attached to your first-level user ID. If the service files have not been loaded, you must load the provided RSU tape by following substep 3 on page 50.

```

attach diskaddr * diskaddr
Ready;

```

```

access diskaddr z
Ready;

```

- b. Obtain the file names of the RSU envelopes on the minidisk (*diskaddr*).

```

listfile * * z
610xRSUn envft z
610xRSUn envft z

```

x RSU number.
n Volume number.

- c. Copy the service files to the MAINT 500 disk and decompress the VMSES/E envelope file.

```

access 500 c
Ready;
deterse 610xRSUn envft z = servlink c

```

You need to enter the DETERSE command for every envelope file you receive with your order.

- d. IPL CMS.

```

ipl cms
z/VM V6.1.0 yyyy-mm-dd hh:mm

```

```

ENTER
Ready; T=n.nn/n.nn hh:mm:ss

```

- e. Access the 500 minidisk containing the servlink.

```

access 500 c
Ready;

```

- f. Run SERVICE.

Run SERVICE

```
service all envfn1 envfn2 ...
VMFSRV2760I SERVICE processing started
:
VMFSRV2760I SERVICE processing completed
successfully
Ready; T=n.nn/n.nn hh:mm:ss
```

List the file names of each PTF or RSU envelope. You can specify more than one envelope file if the RSU is a multivolume only.

envfn1

File name for the first envelope.

envfn2 ...

File name for the second envelope, and so on.

5. View the SERVICE messages log (VMFVIEW SERVICE) and handle any nonzero return codes. Base your actions on the following table:

If you received . . .	Then . . .
Return code 4	<ol style="list-style-type: none">1. Issue VMFVIEW SERVICE.2. Ignore any warning messages listed in the note below. Take appropriate actions based on other warning messages you receive.3. Go to “Step 7. Run PUT2PROD” on page 53.
A return code greater than 4	<ol style="list-style-type: none">1. Issue VMFVIEW SERVICE and check for warning and error messages.2. Ignore any warning messages listed in the note below. Take appropriate actions based on other warning messages you receive.3. Correct all errors reported in the error messages.4. Restart by issuing the SERVICE command as displayed in the message VMFSRV2310W.5. If you receive a nonzero return code, repeat substep 5.6. Go to “Step 7. Run PUT2PROD” on page 53.

Note: You can ignore the following messages and their associated VMF1966W message.

- DMSLI0201W The following names are undefined: ISPLINK ARIPRDI
- DMSLI0201W The following names are undefined: DMSDSCSC
- DMSLI0201W The following names are undefined: DMSUSRX1 DMSUSRX2
- DMSLI0202W Duplicate identifier (Associated with object IOACMAIN MODULE.)
- DMSLKD004W Warning messages issued (Associated with objects ILBONBL, ILBONTR, ILBOREC, ILBORNT, ILBOSND, ILBOSNT, and ILBOSSN.)
- VMFSRV1221W The Stand Alone Dump Utility must be rebuilt.

6. Use the VMFUPDAT SYSMEMO command to review any memos that were received with this service.
7. If the PSP bucket contains COR service that should be applied at install, repeat “Step 6. Run SERVICE” on page 50 to install the service using COR in place of RSU.

Step 7. Run PUT2PROD

In this step, you will:

- Run PUT2PROD to place the product into production.

1. Log on as MAINT.

```

ENTER
logon maint
:
Ready; T=n.nn/n.nn hh:mm:ss

```

The default password for MAINT is MAINT.

2. Make sure the file pool is available.

If you receive message DMS1153E, indicating the MAINT file pool is unavailable or unknown, you need to XAUTOLOG VMSEVS, VMSERVU, and VMSERVR.

```

query limits all
Userid  Storage Group 4K Block Limit 4K Blocks Committed Threshold
userid1      2          n          n-nn%   nn%
userid2      2          n          n-nn%   nn%
:
Ready; T=n.nn/n.nn hh:mm:ss

```

3. IPL CMS and access the VMSES/E test build disk.

```

ipl cms
z/VM V6.1.0   yyyy-mm-dd hh:mm

```

```

ENTER
Ready; T=n.nn/n.nn hh:mm:ss

```

```

access 5E6 b
Ready;

```

4. Run PUT2PROD.

```

put2prod
VMFP2P2760I PUT2PROD processing started
:
VMFP2P2760I PUT2PROD processing completed successfully
Ready; T=n.nn/n.nn hh:mm:ss

```

5. Handle a nonzero return code. Base your action on the following table.

If you received . . .	Then . . .
Return code 4	<ol style="list-style-type: none"> Issue VMFVIEW PUT2PROD. Ignore any warning messages listed in the note below. Take appropriate actions based on other warning messages you receive.

Run PUT2PROD

If you received . . .	Then . . .
A return code greater than 4	<ol style="list-style-type: none"><li data-bbox="568 210 1427 252">1. Issue VMFVIEW PUT2PROD and check for warning and error messages.<li data-bbox="568 252 1427 315">2. Ignore any warning messages listed in the note below in this table. Take appropriate actions based on other warning messages you receive.<li data-bbox="568 315 1427 357">3. Correct all errors reported in the error messages.<li data-bbox="568 357 1427 399">4. Issue IPL CMS.<li data-bbox="568 399 1427 441">5. Issue PUT2PROD.<li data-bbox="568 441 1427 472">6. If you receive a nonzero return code, repeat substep 5 on page 53.

Note: You can ignore the following messages.

- DMSDCS1083E Saved segment \$\$DMY\$\$ does not exist
- DMSWLG292W Text data will be loaded at '20000'x in user area; user data may be overwritten.
- DTCPRD3043W File *fn ft fm* has been updated; It's contents should be reviewed for changes that may affect your use of this file.
- TCPMSM0002W File TCPIP DATA cannot be located
- TCPMSM0002W TCP/IP appears not to have been configured

Step 8. Shut Down and Re-IPL the System

In this step, you will:

- Shut down the V6.1 system.
- IPL the V6.1 system using the new CP nucleus.

1. Shut down and re-IPL the V6.1 system.

shutdown reipl

SYSTEM SHUTDOWN STARTED
Ready; T=*n.nn/n.nn hh:mm:ss*

The shut down message is displayed on all enabled consoles.

HCPWRP963I STARTING SHUTDOWN STEP . . .
:
HCPWRP962I VM SHUTDOWN COMPLETED IN *nn* SEC
HCPWRP9277I SYSTEM TERMINATION COMPLETE,
ATTEMPTING RESTART

HCP963I, HCP962I, and HCP9277I will appear on the operator's console.

hh:mm:ss HCPWRP9277I SYSTEM TERMINATION COMPLETE.
ATTEMPTING RESTART

hh:mm:ss z/VM SYSTEM RESTART FROM SHUTDOWN REIPL

hh:mm:ss z/VM V6 R1.0
SERVICE LEVEL *nnnn* (64-BIT)

hh:mm:ss SYSTEM NUCLEUS CREATED ON *yyyy-mm-dd* AT *hh:mm:ss*,
LOADED FROM 610RES

hh:mm:ss *****

hh:mm:ss * LICENSED MATERIALS - PROPERTY OF IBM* *

hh:mm:ss * 5741-A07 (C) COPYRIGHT IBM CORP. 1983, *

hh:mm:ss * 2009. ALL RIGHTS RESERVED. *

hh:mm:ss * US GOVERNMENT USERS RESTRICTED RIGHTS - *

hh:mm:ss * USE, DUPLICATION OR DISCLOSURE *

hh:mm:ss * RESTRICTED BY GSA ADP SCHEDULE CONTRACT *

hh:mm:ss * WITH IBM CORP. *

hh:mm:ss *

hh:mm:ss * * TRADEMARK OF INTERNATIONAL BUSINESS *

hh:mm:ss * MACHINES *

hh:mm:ss *****

hh:mm:ss HCPZC06718I Using parm disk 1 on volume *valid* (device *xxxx*).

hh:mm:ss HCPZC06718I Parm disk resides on cylinders *xx* through *xx*.

:
:

Attention: If you receive informational message HCPIS954I, you have duplicate DASD with the same label and *must correct* this error before continuing.

hh:mm:ss The directory on volume 610RES at address *nnnn*
has been brought online.

hh:mm:ss HCPWRS2513I

hh:mm:ss HCPWRS2513I Spool files available {*nnnn*|none}

hh:mm:ss HCPWRS2512I Spooling initialization is complete.

:
:

hh:mm:ss FILES: *nnn* RDR, *nnn* PRT, *nnn* PUN

hh:mm:ss LOGON AT *hh:mm:ss* {EST|EDT} *weekday mm/dd/yy*

:
:

hh:mm:ss HCPIOP952I *nnnn*M system storage

hh:mm:ss FILES: *nnnnnnn* RDR, *nnnnnnn* PRT, NO PUN

Shut Down and Re-IPL the System

Message HCP952I tells you the amount of storage available.

The FILES message refers to operator spool files.

CP automatically disconnects from the primary system operator user ID (OPERATOR).

```
hh:mm:ss HCPUS0967I Disconnect OPERATOR - system
          restarted SHUTDOWN and system console
          not VM operator console
```

```
hh:mm:ss HCPCRC8082I Accounting records are accumulating for userid DISKACNT
```

```
hh:mm:ss DISCONNECT AT hh:mm:ss {EST|EDT} weekday mm/dd/yy
```

```
hh:mm:ss Press enter or clear key to continue
```

ENTER

Press Enter or the Clear key to continue.

2. Log on as MAINT.

```
logon maint
```

```
⋮
```

```
Ready; T=n.nn/n.nn hh:mm:ss
```

The password for MAINT is MAINT.

What to do next

See Part 3, "Post z/VM System Installation," on page 129.

Part 2. z/VM System Image DVD Installation

Part 2 contains procedures for installing z/VM from DVD distribution media. If you are installing z/VM from tape distribution media, use Part 1, “z/VM System DDR Installation,” on page 1.

In this part, you will:

- Plan your installation from DVD.
- Fill in worksheets.
- Install the z/VM System image from DVD.

z/VM System image Installation

Chapter 4. Plan Your DVD Installation

In this chapter, you will

- Plan your installation.
- Fill in the installation worksheet and the TCP/IP configuration worksheet.

Step 1. Review and Comply with the Requirements

Before you install V6.1, you must satisfy the following requirements:

1. z/VM media deliverable
 - Be sure you have both the installation DVD and the RSU DVD.
 - If the RSU (or COR) service is electronic or on CD-ROM you need to receive the service files to a minidisk attached to your installation user ID before IPLing your second-level system. Follow the instructions included with the electronic or CD-ROM service files to receive and restore the service files to a minidisk that can be temporarily attached to your second-level system.
2. General
 - A processor supported by z/VM version 6 release 1. For a list of processors supported by z/VM, see *z/VM: General Information*.
 - For instructions on how to receive up-to-date service, see the Program Directory for z/VM.
 - For up-to-date information affecting installation, see the "installation information" section in the CP subset of the zvm610 upgrade PSP bucket.
 - If you plan to migrate from another z/VM system, review *z/VM: Migration Guide*.
 - If you plan to deploy Linux on z/VM, see *z/VM: Getting Started with Linux on System z* for important planning information about Linux virtual servers.
 - The z/VM FTP installation procedure complies with the FTP client protocol standards described in RFC 959 and RFC 1123. Passive FTP data transfers are used in order to minimize the affects of intervening firewall systems, so your FTP server must support the PASV command.
3. Installation methods
 - **First-level installation** can be done from a DVD drive attached to the Hardware Management Console (HMC), a DVD drive connected through an FTP server, or from an FTP server where the files from the DVD have been placed in an FTP accessible directory.
 - Hardware requirements
 - Exclusive access to your processor's service element (SE) in order to load your z/VM starter system to RAM.
 - Access to the integrated 3270 console on the HMC (CONS=SYSG) for use as the console during first-level install.
 - At least 768 MB of real storage assigned to the LPAR where z/VM will be installed.
 - Note:** The storage required for installation is not necessarily the amount you should have assigned for running production workloads. See *z/VM: CP Planning and Administration* for information on determining production storage requirements.
 - FTP server requirements
 - The server must comply with RFC 959 and RFC 1123.
 - The server must be able to communicate with both the HMC and primary SE of the LPAR where you will install. This means that both the HMC and primary SE must be enabled for TCP/IP communication, including any required firewall authorizations, and authorized to use FTP.
 - The server must be able to access a DVD drive or a directory where the contents of the DVD will be stored.
 - If installing from an FTP server directory, the server must have at least 3 GB of available space to store the contents of the z/VM system DVD and the RSU DVD. The contents of the z/VM system DVD and the RSU DVD must be stored in same directory.
 - HMC and support element considerations
 - If you wish to use a HMC's DVD drive, then the HMC must communicate with the desired support element. HMCs can only communicate with support element versions that are equal

to or lower than themselves. For example, an HMC version 1.8.0 can communicate with a support element at version 1.7.3, or 1.8.0, but it can not communicate with a support element at version 1.8.2.

- **Second-level installation** can be done from a DVD drive connected through an FTP server, from an FTP server where the files from the DVD have been placed in an FTP accessible directory, or from a VM minidisk.

To install using the DVD drive installation method, you must use a DVD drive connected through an FTP server. To install using the FTP server directory installation method, you must upload the contents of the DVD to a directory on the server. To install using the VM minidisk installation method, you must upload the contents of the DVD to a minidisk that is CMS-formatted and can be accessed by your installation user ID.

- Hardware requirements
 - A first-level system running at least z/VM V5.
 - Access to a local non-SNA 3270 terminal, or equivalent, configured with at least 24 lines, or an integrated 3270 console.
- FTP server requirements
 - The server must comply with RFC 959 and RFC 1123.
 - The server must have a TCP/IP communication path to the system you are using to install.
 - The server must be able to access a DVD drive or a directory where the contents of the DVD will be stored.
 - If installing from an FTP server directory, the server must have at least 3 GB of available space to store the contents of the z/VM system DVD and the RSU DVD. The contents of the z/VM system DVD and the RSU DVD must be stored in same directory.
- User ID requirements
 - Access to the INSTPIPE module on your current system. The module is shipped on the MAINT 2CC disk.
 - Privilege classes of at least B and G.
 - At least 64 MB of virtual storage.
 - A 191 read/write minidisk accessed as file mode A.
 - A 2222 read/write minidisk, matching the supported DASD type of your installation DVD, that is exactly:
 - 5 cylinders (3390) or
 - 7200 512-KB blocks (fba)
 - A 22CC read/write minidisk, matching the supported DASD type of your installation DVD, that is exactly:
 - 5 cylinders (3390) or
 - 7200 512-KB blocks (fba)
 - A 2CF1 read/write minidisk, matching the supported DASD type of your installation DVD, that is exactly:
 - 120 cylinders (3390) or
 - 172800 512-KB blocks (fba)
 - If installing from a VM minidisk, access to a CMS-formatted minidisk that is at least 4500 cylinders of 3390 DASD.

Step 2. Complete the Installation and Basic IP Connectivity Worksheets

1. Determine the installation method you will use.
 - Choose first-level installation if no supported z/VM system is running on the processor or LPAR on which you are installing.
 - Choose second-level installation if you are installing in a virtual machine on a supported z/VM system.
2. Record the installation method you selected to use to install z/VM in the installation worksheet (Table 8 on page 64). Your choices are first-level or second-level.
3. Determine which products you will load into the VMSYS file pool and which products you will load to minidisks only. Each product on the z/VM system DVD allows VMSYS file pool directories to be used in place of some minidisks. Record your choices in the installation worksheet (Table 8 on page 64).
4. Select your system default language and record your choice in the installation worksheet (Table 8 on page 64). The choices are:
 - Mixed Case English (AMENG)
 - Uppercase English (UCENG)
 - Kanji (KANJI)
5. Select the DASD type and model you will use to install, and record the DASD information on the "DASD Type and Model" line in the installation worksheet (Table 8 on page 64). If you are using the:
 - FBA (SCSI) DVD, record FBA for the DASD model.
 - 3390 DVD, record either 3390 Model 3 or 3390 Model 9.For performance reasons, IBM recommends using emulated 3390 Model 9s instead of real 3390 Model 9s.

Notes:

- a. DASD size is not checked during installation.
 - b. If you select 3390 Model 3, installation uses the first 3338 cylinders on each DASD and ignores any cylinders beyond 3338.
 - c. If you select 3390 Model 9, installation uses the first 10017 cylinders on each DASD and ignores any cylinders beyond 10017.
 - d. If you select FBA DASD, installation uses up to the size entered on the INSTPLAN panel.
6. Estimate the number of DASD volumes required to install. If you choose:
 - 3390 DASD, you will need:
 - 3390 Model 3, five volumes.
 - 3390 Model 9, three volumes.If you selected to install products to a combination of the VMSYS file pool and minidisks in substep 3, you might need an extra volume depending on where you choose to install each product.
 - FBA (SCSI), you will need:
 - One volume each for 610PAG and 610SPL. These volumes can be any size (minimum of 1 GB) and will be fully allocated.
 - One volume for 610RES. This volume should be an FBA disk with a minimum of 3.5 GB of space.
 - Up to two volumes for 610W01 and 610W02 depending on the size of 610RES. These volumes should be at least as large as 610RES because the installation programs assumes they are all the same size.

Complete the Installation and Basic IP Connectivity Worksheets

Notes:

- a. INSTPLAN, which is run early in the installation procedure, will tell you exactly how many volumes are required.
 - b. INSTPLAN will ask for the 610RES FBA disk size. The size must be at least 3.5 GB. If you are using a disk larger than 10 GB, installation will use up to 10 GB only. IBM suggests that you do not use any left over space on 610RES. Record the size on the “SCSI Disk Size” line of the installation worksheet (Table 8 on page 64).
7. If you are using FBA (SCSI) disks, and they are already defined, you need only the DASD addresses of the volumes and can continue to the next substep. If they are not already defined, you need to know the WWPN and LUN address for each disk, as well as either the valid FCP address(es) or the channel path (CHPID) they belong to. Record each LUN and its corresponding WWPN in the SCSI Device Definition Worksheet (Table 9 on page 64). Also make a note of the valid FCP address(es) or CHPID.
 8. Record the DASD addresses for each DASD you selected in the installation worksheet (Table 8 on page 64) under the *DASD Address* column. Record your first address in the row with the label “610RES” and continue recording addresses corresponding to the labels. If you need fewer than all the DASD labels in the table, disregard the extra labels.
 9. If you are changing the installation pack labels, record the new pack labels in the installation worksheet (Table 8 on page 64).
For each default label you wish to change, record the new label in the installation worksheet (Table 8 on page 64) under the *New Label* column. The label, 610RES, cannot be changed.
 10. If, after you install z/VM, you want to establish a minimal TCP/IP configuration that establishes basic connectivity to your IP network, fill in the IP worksheets beginning with Table 10 on page 65 and then return here.

What to do next

Base your choice on the installation method that fits your situation.

If you chose the . . .	Then see . . .
First-level installation method	Chapter 5, “First-Level DVD Installation Method,” on page 67
Second-level installation method	Chapter 6, “Second-Level DVD Installation Method,” on page 91

Worksheets

Table 8. DVD Installation Worksheet

Installation method (first-level or second-level): _____					
Install To column: record an "M" if you will load the product to a minidisk or an "F" if you will load the product to the VMSYS file pool.					
Install To	Product	Install To	Product	Install To	Product
	VM		OSA		PERFTK
	VMHCD		RACF		DIRM
	RSCS		ICKDSF		TCPIP
System default language: _____ DASD type and model: _____ SCSI disk size: _____ GB					
Pack Type	DASD Label	New Label	DASD Address		
RES	610RES	610RES			
SPOOL	610SPL				
PAGE	610PAG				
USER1	610W01				
USER2	610W02				
USER3	610W03				
DVD/FTP directory path name: _____ Address of VM minidisk to upload DVD: _____					

Table 9. SCSI Device Definition Worksheet (DVD Installation)

DASD	edevic address	fcp address	WWPN	LUN
610RES				
610SPL				
610PAG				
610W01				
610W02				
610W03				
Channel path (CHPID): _____ Valid FCP addresses: _____				

Complete the Installation and Basic IP Connectivity Worksheets

After you have completed your z/VM installation, you can optionally create a minimal TCP/IP configuration that establishes basic connectivity to your IP network. If you choose to perform this configuration, you must gather the following information from your network system administrator and record the information in Table 10 and the appropriate interface worksheet. In these worksheets, a number in parentheses following a field description, for example “Host name (20),” is the maximum length for that field.

Note: The IP configuration wizard supports real network devices only. If you plan on using virtual network devices for TCP/IP, they must be configured manually. See *z/VM: TCP/IP Planning and Customization*.

Table 10. DVD Installation TCP/IP Configuration Worksheet

z/VM user ID of the z/VM TCP/IP stack virtual machine: (Default value is TCPIP. If you change this user ID, you must define the user ID in your user directory before running the IPWIZARD.)	
Host name (20):	
Domain name (40):	
DNS IP address (up to three addresses) :	1) _____ 2) _____ 3) _____
Gateway IP address :	
Interface name (16):	
Device number:	
IP address:	
IPv4 subnet mask (15) or IPv6 prefix length (3):	
Path MTU discovery (IPv4 interfaces):	<input type="checkbox"/> Enabled <input type="checkbox"/> Disabled
Choose the interface you will be using (check one):	<input type="checkbox"/> QDIO (layer 3) <input type="checkbox"/> QDIO (layer 2) <input type="checkbox"/> LCS <input type="checkbox"/> HiperSockets <input type="checkbox"/> CLAW <input type="checkbox"/> CTC Refer to the appropriate worksheet to record more information. IPv6 is available only for QDIO and HiperSockets devices.

Table 11. QDIO Interface Worksheet (DVD Installation)

Network type (select one):	<input type="checkbox"/> Ethernet <input type="checkbox"/> Token Ring IPv6 is not available for Token Ring adaptors.
Port name (optional) (8):	

Complete the Installation and Basic IP Connectivity Worksheets

Table 11. QDIO Interface Worksheet (DVD Installation) (continued)

Router type (select one):	<input type="checkbox"/> Primary <input type="checkbox"/> Secondary <input type="checkbox"/> None Router type is not available for layer 2 transport.
Maximum transmission unit (MTU) size:	
Router advertisements (IPv6 only):	<input type="checkbox"/> On <input type="checkbox"/> Off
Port number (optional):	

Table 12. LCS Interface Worksheet (DVD Installation)

Network type (select one):	<input type="checkbox"/> Ethernet <input type="checkbox"/> Token Ring <input type="checkbox"/> FDDI
Port/adaptor number:	
Maximum transmission unit (MTU) size:	

Table 13. HiperSockets Interface Worksheet (DVD Installation)

Maximum frame size (MFS): (in kilobytes)	
Router advertisements (IPv6 only)	<input type="checkbox"/> On <input type="checkbox"/> Off

Table 14. CLAW Interface Worksheet (DVD Installation)

CLAW host name (8): (This name must match the host-name configured on the CLAW device)	
CLAW adapter name (8): (This name must match the device-name configured on the CLAW device)	
Maximum transmission unit (MTU) size:	

Table 15. CTC Interface Worksheet (DVD Installation)

Write channel device number (select one):	<input type="checkbox"/> This choice contains the device number specified on the main z/VM TCP/IP Configuration Wizard panel. <input type="checkbox"/> This choice contains the device number specified on the main z/VM TCP/IP Configuration Wizard panel plus 1.
Maximum transmission unit (MTU) size:	
Peer IP address:	

Chapter 5. First-Level DVD Installation Method

In this chapter, you will:

- Use step-by-step procedures to install the first-level z/VM System Image DVD in a new system environment.

Step 1. Load the RAMDISK

In this step, you will:

- Load the RAM disk from DVD.
- Start the RAMDISK system.

Note: Make sure that any DASD with the same labels you are using for installation are not attached to your system.

Before you begin: You need to complete the installation worksheet (Table 8 on page 64).

1. Prepare to access the installation files.

If installing from a:

- HMC DVD drive, load the z/VM system DVD in the HMC DVD drive.
- FTP server DVD drive, load the z/VM system DVD in the FTP connected DVD drive.
- FTP server directory, upload the contents of both the z/VM system DVD and the RSU DVD to a new directory on the FTP server.
 - a. Create a new directory on the FTP server. The maximum length of the directory path name is 40 characters. The FTP server will need at least 3 GB of free space.
 - b. Upload the contents of each DVD to the directory. After the contents of the z/VM system DVD have been uploaded, upload the contents of the RSU DVD to the same directory, overwriting any duplicate files.

2. On the HMC, open an integrated 3270 console for the LPAR you are going to use for installation.

- a. In the Hardware Management Console Workplace window, double-click the **Groups** icon in the Views pane.
- b. In the Groups Work Area pane, double-click the **CPC Images** icon.
- c. In the CPC Images Work Area pane, select the LPAR you are going to use for installation.
- d. In the Recovery pane, double-click the **Integrated 3270 Console** icon. The Integrated 3270 Console window for that LPAR opens. Messages are displayed in the Integrated 3270 Console window when the system IPLs.

3. Access the primary SE for the LPAR you are going to use for installation.

- a. In the Hardware Management Console Workplace window, double-click the **Groups** icon in the Views pane.
- b. In the Groups Work Area pane, double-click the **Defined CPCs** icon.
- c. In the Defined CPCs Work Area pane, select the processor you are going to use for installation.
- d. In the Recovery pane, double-click the **Single Object Operations** icon. The Single Operation Task Confirmation prompt is displayed.
- e. Click **Yes** to continue. The Primary Support Element Workplace window opens. You now have control of the primary SE.

4. On the primary SE, select the icon labeled either **Load from CD-ROM, DVD or Server** or **Load from Removable Media or Server** in the Recovery pane for the LPAR you are going to use for installation.

- a. In the Primary Support Element Workplace window, double-click the **Task List** icon in the Views pane.
- b. In the Task List Work Area pane, double-click the **CPC Recovery** icon.

- c. In the Views pane, double-click the **Groups** icon.
 - d. In the Groups Work Area pane, double-click the **Images** icon.
 - e. In the Images Work Area pane, select the LPAR you are going to use for installation.
 - f. In the Recovery pane, double-click the icon labeled either **Load from CD-ROM, DVD or Server** or **Load from Removable Media or Server**. The Task Confirmation prompt is displayed.
 - g. Click **Yes** to continue.
5. In the task window, select one of the following:
- Hardware Management Console CD-ROM / DVD
 - FTP Source
- If you are installing from the HMC DVD drive, select **Hardware Management Console CD-ROM / DVD**. Otherwise, if you are installing from an FTP server DVD drive or from an FTP server directory, select **FTP Source**.
- Note:** If you are installing from an FTP server directory, both the z/VM system DVD and the RSU DVD must have been copied into the same directory on the FTP server.
6. Fill in the fields in the task window.
- If you selected **Hardware Management Console CD-ROM / DVD**, enter /CPDVD as the file location.
 - If you selected **FTP Source** and you are using an FTP server DVD drive:
 - Specify the FTP connection information for the server.
 - Enter the drive letter for the FTP server DVD drive, followed by /CPDVD, as the file location.
 - If you selected **FTP Source** and you are using an FTP server directory:
 - Specify the FTP connection information for the server.
 - Enter the path to the directory where you uploaded the z/VM system DVD and RSU DVD as the file location.
- Note:** If using a DVD drive, wait until the light on the drive goes out or stops blinking before continuing.
7. Load the RAMDISK.
- a. In the task window, select the Software to Load window, select **610VM.ins**, and click **Continue**. The Confirm the Action prompt is displayed.
 - b. Click **Yes** to continue.
 - c. Messages indicating the status of the load are displayed in the task progress window. When a message is displayed indicating the load is successful, click **OK** to close the window and return to the Integrated 3270 Console window for the LPAR you are going to use for installation.
8. The RAMDISK IPLs and the system loads with the MAINT user ID logged on. System messages are displayed in the Integrated 3270 Console window.

Load the RAMDISK

```
hh:mm:ss z/VM V6 R1.0
        SERVICE LEVEL nnnn (64-BIT)

hh:mm:ss SYSTEM NUCLEUS CREATED ON yyyy-mm-dd AT hh:mm:ss,
        LOADED FROM $RAMD$
hh:mm:ss *****
hh:mm:ss * LICENSED MATERIALS - PROPERTY OF IBM* *
hh:mm:ss * 5741-A07 (C) COPYRIGHT IBM CORP. 1983, *
hh:mm:ss * 2009. ALL RIGHTS RESERVED. *
hh:mm:ss * US GOVERNMENT USERS RESTRICTED RIGHTS - *
hh:mm:ss * USE, DUPLICATION OR DISCLOSURE *
hh:mm:ss * RESTRICTED BY GSA ADP SCHEDULE CONTRACT *
hh:mm:ss * WITH IBM CORP. *
hh:mm:ss * *
hh:mm:ss * * TRADEMARK OF INTERNATIONAL BUSINESS *
hh:mm:ss * MACHINES *
hh:mm:ss *****
hh:mm:ss HCPZC06718I Using parm disk 1 on volume $RAMD$ (device xxxx).
hh:mm:ss HCPZC06718I Parm disk resides on blocks xxx through xxx.
                                The system logs on the MAINT user ID.

hh:mm:ss The directory on volume $RAMD$ at address nnnn
        has been brought online.

hh:mm:ss HCPWRS2512I Spooling initialization is complete.
hh:mm:ss No dump unit - Dump function is SET OFF
hh:mm:ss HCPAAU2700I System gateway IBMVMRAM identified.
hh:mm:ss z/VM Version 6 Release 1.0, Service Level 0000 (64-bit),
built on IBM Virtualization Technology
hh:mm:ss There is no logmsg data
hh:mm:ss FILES: NO RDR, NO PRT, NO PUN
hh:mm:ss LOGON AT hh:mm:ss EDT DAY mm/dd/yy
hh:mm:ss SYSG LOGON AS MAINT USERS = n
hh:mm:ss HCPiop952I nnnnM system storage
hh:mm:ss FILES: nnnnnnnn RDR, nnnnnnnn PRT, NO PUN
hh:mm:ss HCPCRC8082I Accounting records are accumulating for userid OPERACCT
hh:mm:ss HCPCRC8082I EREP records are accumulating for userid OPERACCT

DMSIND2015W Unable to access the Y-disk. File mode Y (19E) not accessed
DMSWSP327I The installation saved segment could not be loaded
z/VM V6.1.0 yyyy-mm-dd hh:mm
DMSDCS1083E Saved segment CMSPIPES does not exist
DMSDCS1083E Saved segment CMSPIPES does not exist
DMSDCS1083E Saved segment CMSVLIB does not exist
Ready; T=n.nn/n.nn hh:mm:ss
```

9. Log off the primary SE.

In the Primary Support Element Workplace window, click the **X** in the upper-right corner to log off.

Step 2. Run INSTPLAN

In this step, you will:

- Run INSTPLAN.

1. Run INSTPLAN.

```
instplan
**** NOW EXECUTING INSTPLAN EXEC ON date AT time ****
```

```

*** z/VM INSTALLATION PLANNING ***

Mark the product(s) selected to be installed into the VMSYS filepool with an
"F" and those selected to be installed to minidisks with an "M"

Install To  Product      Install To  Product      Install To  Product
-----
M          VM          M          OSA          M          PERFTK
M          VMHCD       M          RACF         M          DIRM
M          RSCS        M          ICKDSF       M          TCPIP

Place a nonblank character in front of the System Default Language you would
like for your system.

_ AMENG      _ UCENG      _ KANJI

Place a nonblank character in front of the DASD model onto which your
z/VM system will be loaded. Only one model may be selected.

_ 3390 Mod 3   _ 3390 Mod 9   _ FBA DASD 3.5

PF1 = HELP   PF3/PF12 = QUIT   PF5 = Process   ENTER = Refresh

```

Figure 5. Installation Planning Panel

- See the installation worksheet (Table 8 on page 64) and enter:
 - An “M” in the **Install To** column for each product you selected to be installed onto minidisks.
 - An “F” in the **Install To** column for each product you selected to be installed into the VMSYS file pool.
- Place a nonblank character next to the System Default Language you selected for your system (see the installation worksheet, Table 8 on page 64).
- Place a nonblank character in front of the DASD model that matches the *DASD type and model* recorded on the installation worksheet (Table 8 on page 64). If you are installing to FBA (SCSI), the size of the FBA disk must be at least 3.5 GB.
- Press F5 to process your selections.

Run INSTPLAN

Note: The output you see may be different due to your planning choices.

F5

```
HCPIPX8475I THE PRODUCTS YOU SELECTED TO LOAD TO MINIDISK ARE:  
VM RSCS TCPIP OSA ICKDSF  
DIRM RACF PERFTK VMHCD
```

```
THE PRODUCTS YOU SELECTED TO LOAD TO SFS ARE:  
NONE
```

```
THE SYSTEM DEFAULT LANGUAGE SELECTED:  
AMENG
```

```
THE DASD TYPE YOU SELECTED TO LOAD ON IS:  
type
```

```
THE DASD NEEDED TO LOAD z/VM ARE:  
610RES 610SPL 610PAG...
```

```
HCPINP8392I INSTPLAN EXEC ENDED SUCCESSFULLY  
Ready; T=n.nn/n.nn hh:mm:ss
```

2. Make sure the number of DASD selected on the installation worksheet (Table 8 on page 64) matches the number of DASD listed in the HCPIPX8475I message.

Step 3. Verify the Volumes Needed for Installation are Available

In this step, you will:

- Attach the volumes needed for installation.

1. If you are installing to 3390 skip to substep 7 on page 74.
2. See the installation worksheet (Table 8 on page 64) and query each DASD address to verify it is not already defined for a different device (see example below). If the address is already in use, choose a different *dasdaddr* and verify that address does not exist.

For each DASD address:

```
query dasdaddr
HCPQVD040E Device dasdaddr does not exist
Ready(00040);
```

Record each verified DASD address in the DASD Address column of the installation worksheet (Table 8 on page 64) and in the “edevice” column of the SCSI device definition worksheet (Table 9 on page 64).

3. To define the SCSI disks, you need to know which FCP addresses are valid for your SCSI disks.

If you know the FCP addresses associated with your SCSI disk addresses skip to substep 4.

If only the channel path id is known, issue the Query CHPID command to display all FCP addresses associated with the path. For example, if the channel path is X'66', issue:

```
query chpid 66
Path 66 online to devices 517C 5319 550D 8100 8101 8102 8103 8104
Path 66 online to devices 8105 8106 8107 8108 8109 810A 810B 810C
Path 66 online to devices 810D 810E 810F 8110 8111 8112 8113 8114
Path 66 online to devices 8115 8116 8117 8118 8119 811A 811B 811C
Path 66 online to devices 811D 811E 811F
```

4. To define the SCSI disks, use the information recorded in the installation worksheet (Table 8 on page 64) and SCSI device definition worksheet (Table 9 on page 64).

For each DASD:

- a. Select and record a free FCP address for each *edev*. You should use one FCP device for the 610RES and a different (or multiple different) FCPs for the other disks.

```
query fcp free
```

Choose a device from the output. Record a FCP address for each *edev* in the FCP Address column of the SCSI Device Definition Worksheet (Table 9 on page 64).

- b. Define the device address.

```
set edev dasdaddr type fba attr scsi fcp_dev fcpn wwpn www lun lll
```

Verify the Volumes Needed for Installation are Available

dasdaddr

The edevice address from Table 9 on page 64.

fcpn

FCP address (you should use one FCP device for the 610RES and a different, or multiple different, FCPs for the other disks).

www

World Wide port number.

/// LUN address.

5. Vary on the SCSI disks. Repeat for each disk.

```
vary on dasdaddr
```

6. Note the following change needed in the SYSTEM CONFIG file for future IPLs.

- When performing a first-level installation to SCSI disk, INSTDVD updates the SYSTEM CONFIG file to include EDEV statements that define the SCSI disks you used to install. If you are going to IPL these disks second-level, the EDEV statements need to be commented out of the SYSTEM CONFIG file before attempting to IPL second-level.

For information on updating the SYSTEM CONFIG file, see *z/VM: CP Planning and Administration*.

7. Attach all the DASD listed in the installation worksheet (Table 8 on page 64) that are not already attached. Enter the following ATTACH command for each DASD.

```
attach dasdaddr *  
DASD dasdaddr ATTACHED TO userID dasdaddr  
:  
Ready; T=n.nn/n.nn hh:mm:ss
```

dasdaddr
Address of the DASD.

Step 4. Run INSTDVD

In this step, you will:

- Run INSTDVD.

1. Run INSTDVD to restore the image files to DASD.

```
instdvd
**** NOW EXECUTING INSTDVD EXEC ON date AT time ****
```

```
*** z/VM DVD INSTALL FORMAT/RESTORE PANEL ***
```

PACK TYPE	DASD LABEL	DASD ADDRESS	DO NOT FORMAT DASD
RES	610RES	---	---
SPOOL	610SPL	---	
PAGE	610PAG	---	
USER	610W01	---	
USER	610W02	---	

PF1 = HELP PF3/PF12 = QUIT PF5 = Process ENTER = Refresh

Figure 6. z/VM DVD Install Format and Restore Panel (3390 Model Layout)

- If you want to change the labels of the SPOOL, PAGE, or USER packs, fill in the DASD LABEL field with the new labels. You cannot change the 610RES label. If you are installing second-level and you wish to change installation pack labels, the installation user ID must be able to issue the DEFINE MDISK command. The IBM default privilege class for this command is class A. The DEFINE MDISK command also requires the user ID to have DEVMAINT on the OPTION directory statement in its directory entry.
- Fill in the DASD addresses using the information from the installation worksheet (Table 8 on page 64). For more information and help, press F1.
- Place a nonblank character in the DO NOT FORMAT DASD column only if you have already CP formatted your DASD for this installation using ICKDSF or CPFMTXA. The DASD will be labeled, but not formatted.
- Press F5 to process.

F5

HCPDCX8377R YOU HAVE SELECTED TO FORMAT THE FOLLOWING DASD:

HCPDCX8483R YOU HAVE SELECTED NOT TO FORMAT YOUR DASD.
THIS ASSUMES YOU HAVE ALREADY FORMATTED THE
DASD AND THIS EXEC WILL ONLY RELABEL AS
FOLLOWS

Depending on whether you chose to format your DASD, you will receive either message HCPDCX8377R or HCPDCX8483R.

Run INSTDVD

```
610RES dasdaddr
1b1sp1 dasdaddr
1b1pag dasdaddr
1b1W01 dasdaddr
```

DO YOU WANT TO CONTINUE ? (Y|N)

y

```
HCPDCX8490I NOW {FORMATTING|LABELING} DASD dasdaddr
```

```
HCPDCX8490I NOW {FORMATTING|LABELING} DASD dasdaddr
```

```
⋮
```

```
HCPDCX8380I RESTORING IIS TO 610RES and 1b1sp1
```

```
DVDLOAD: LOADING FILE '{FBAIIS00 | CKDIIS00}' IMAGE *
```

```
DVDLOAD: RC=0
```

```
{ECKDREST|MDREST}: WROTE nnnn {TRACKS|BLOCKS} ON addr, RC=0
```

```
HCPDCX8341I LOAD OF THE SYSTEM IIS COMPLETED SUCCESSFULLY
```

```
DVDLOAD: LOADING FILE '{FBASPL00 | CKDSPL00}' IMAGE *
```

```
⋮
```

```
DVDLOAD: LOADING FILE '{FBASPLnn | CKDSPLnn}' IMAGE *
```

```
DVDLOAD: RC=0
```

```
{ECKDREST|MDREST}: WROTE nnnn {TRACKS|BLOCKS} ON addr, RC=0
```

```
HCPDCX8341I LOAD OF THE SYSTEM SPOOL SPACE COMPLETED SUCCESSFULLY
```

```
HCPDCX8490I NOW ALLOCATING DASD addr (RES PACK)
```

```
HCPDCX8490I NOW ALLOCATING DASD addr (SPOOLING)
```

```
HCPDCX8490I NOW ALLOCATING DASD addr (PAGING)
```

The minidisks with the END option specified in this directory will not be included in the following DISKMAP file.

File USER DISKMAP A has been created.

```
HCPIND8392I INSTDIR EXEC ENDED SUCCESSFULLY
```

```
HCPIDV8341I CREATION OF USER DIRECTORY COMPLETED SUCCESSFULLY
```

Messages received for each minidisk loaded

```
HCPILB8440I NOW LOADING {FBAcuu | CKDcuu}, DISK xxx OF yyy
```

```
DVDLOAD: LOADING FILE '{FBAcuu00 | CKDcuu00}' IMAGE *
```

```
⋮
```

```
DVDLOAD: LOADING FILE '{FBAcuunn | CKDcuunn}' IMAGE *
```

```
DVDLOAD: RC=0
```

```
{ECKDREST|MDREST}: WROTE nnnn {TRACKS|BLOCKS} ON addr, RC=0
```

If the install fails while processing disks in this box, enter INSTDVD to retry. INSTDVD will resume where processing failed.

HCPIRU8484R PLEASE PLACE THE SYSTEM RSU DVD IN THE DRIVE, THEN TYPE GO TO CONTINUE OR TYPE EXIT TO QUIT.

If you are using an RSU on DVD, place the DVD in the DVD drive and wait until the light on the DVD drive goes out or stops blinking, then enter GO.

go

If installing from an FTP server, where both the product and RSU DVD contents have been loaded, enter GO.

If you enter EXIT to quit, your installation will not complete successfully. You will need to run the INSTDVD command and enter GO to load the RSU files before you can continue with the installation procedures.

If the install fails while loading the RSU, enter INSTDVD to retry.

```
DVDLOAD: LOADING FILE '{FBA500000|CKD50000} IMAGE *'
:
DVDLOAD: LOADING FILE '{FBA500nn|CKD500nn} IMAGE *'
DVDLOAD: RC=0
{ECKDREST|MDREST}: WROTE nnnn {TRACKS|BLOCKS} ON addr, RC=0
```

```
z/VM USER DIRECTORY CREATION PROGRAM - VERSION 6 RELEASE 1.0
EOJ DIRECTORY UPDATED
HCPDIR494I User directory occupies nn disk pages
HCP6798I VOLUME ID IS 610RES
HCP6797I MINIDISK VOLID AT OFFSET nn IS MNTCF1
HCPIDV8341I SALIPL COMMAND HAS COMPLETED SUCCESSFULLY
hh:mm:ss DASD nnnn ATTACHED TO SYSTEM 610RES BY MAINT
HCP1WF8338I NOW EXECUTING COPY CF1 and 2CC STEP
hh:mm:ss DASD nnnn DETACHED SYSTEM BY MAINT
hh:mm:ss DASD nnnn ATTACHED TO MAINT nnnn BY MAINT WITH DEVCTL
HCPIDV8376I INSTDVD EXEC ENDED SUCCESSFULLY
Ready;
```

Step 5. IPL the new z/VM System

In this step, you will:

- IPL the new z/VM system.

1. On the HMC, IPL the new z/VM system you loaded to 610RES.
 - a. In the Hardware Management Console Workplace window, double-click the **Groups** icon in the Views pane.
 - b. In the Groups Work Area pane, double-click the **CPC Images** icon.
 - c. In the CPC Images Work Area pane, select the LPAR you are using for installation.
 - d. In the Recovery pane, double-click the **Load** icon.
 - e. In the Load window:
 - If installing on 3390:
 - 1) Select **Normal**.
 - 2) In the **Load address** field, enter the address of 610RES.
 - 3) In the **Load parameter** field, enter SYSG.
 - 4) Click **OK**.
 - If installing on FBA (SCSI):
 - 1) Select **SCSI**.
 - 2) In the **Load address** field, enter the address of the FCP (that is, the FCP address not the EDEV address) used to define 610RES.
 - 3) In the **Load parameter** field, enter SYSG.
 - 4) In the **Worldwide port name** field, enter the name used to define 610RES.
 - 5) In the **Logical unit number** field, enter the 16 character LUN address of 610RES.
 - 6) In the **Boot program selector** field, enter 0 (zero).
 - 7) In the **Boot record logical block address** field, enter the 16 character value 00000000000000C8.
 - 8) Click **OK**.
 - f. Click **Yes** to continue.
 - g. Messages indicating the status of the load are displayed in the Load Progress window. When a message is displayed indicating the load is successful, click **OK** to close the window and return to the Integrated 3270 Console window for the LPAR you are using for installation.

The Stand Alone Program Loader panel displays on the integrated 3270 console after issuing the IPL command.


```

STAND ALONE PROGRAM LOADER: z/VM VERSION 6 RELEASE 1.0

DEVICE NUMBER:  dasdaddr  MINIDISK OFFSET:  nnnnnnnn  EXTENT:  1
MODULE NAME:    CLOAD    LOAD ORIGIN:      2000

-----IPL PARAMETERS-----
cons=sysg pdvol=edevaddr

-----COMMENTS-----

-----

9= FILELIST  10= LOAD  11= TOGGLE EXTENT/OFFSET

```

Figure 7. Sample Stand Alone Program Loader Panel

2. Move the cursor to the IPL PARAMETERS field and enter:

```
cons=sysg pdvol=edevaddr
```

Note: If using 3390, do not use `pdvol=edevaddr`.

```
dasdaddr
```

Device address of 610RES (as shown in Figure 7) for 3390 or the FCP address for the SCSI (FBA).

```
edevaddr
```

Device address of 610RES for SCSI (FBA).

3. Press F10 to load.

F10

```

hh:mm:ss z/VM V6 R1.0
          SERVICE LEVEL nnnn (64-BIT)

hh:mm:ss SYSTEM NUCLEUS CREATED ON yyyy-mm-dd AT hh:mm:ss,
          LOADED FROM 610RES

hh:mm:ss *****
hh:mm:ss * LICENSED MATERIALS - PROPERTY OF IBM* *
hh:mm:ss * 5741-A07 (C) COPYRIGHT IBM CORP. 1983, *
hh:mm:ss * 2009. ALL RIGHTS RESERVED. *
hh:mm:ss * US GOVERNMENT USERS RESTRICTED RIGHTS - *
hh:mm:ss * USE, DUPLICATION OR DISCLOSURE *
hh:mm:ss * RESTRICTED BY GSA ADP SCHEDULE CONTRACT *
hh:mm:ss * WITH IBM CORP. *
hh:mm:ss * *
hh:mm:ss * * TRADEMARK OF INTERNATIONAL BUSINESS *
hh:mm:ss * * MACHINES *
hh:mm:ss *****
hh:mm:ss HCPZC06718I Using parm disk 1 on volume 610RES (device xxxx).
hh:mm:ss HCPZC06718I Parm disk resides on blocks/cylinders xxx through xxx.

```

IPL the new z/VM system

⋮

You might receive an informational message, HCPIISU951I, about volumes not mounted. If you are not using those volume labels, ignore this message.

Note: If you receive informational message HCPIIS954I for your 610RES volume (for example, DASD 5016 VOLID 610RES IS A DUPLICATE OF DASD 5516), you can ignore this message and proceed. For any other occurrence of HCPIIS954I, you have duplicate volumes with the same label. Make note of the duplicate volumes and enter SHUTDOWN at the next prompt. Relabel the duplicate volumes and then go back to substep 1 on page 78.

```
hh:mm:ss Start ((Warm|Force|COLD|CLEAN) (DRain)
              (Disable) (NODIRect) (NOAUTOlog)) or (SHUTDOWN)
```

cold drain noauto log

Because there is no data or accounting information to recover, use COLD DRAIN to request a cold start. Use NOAUTOLOG at this point because you cannot have the servers and all user IDs logged on.

```
NOW hh:mm:ss {EST|EDT} weekday yyyy-mm-dd
Change TOD clock (yes|no)
```

no

CP logs on the primary system operator user ID (OPERATOR).

```
hh:mm:ss The directory on volume 610RES at address nnnn
         has been brought online.
```

```
hh:mm:ss HCPWRS2513I
```

```
hh:mm:ss HCPWRS2513I Spool files available      nnnn
```

Note: Depending on the type of spool files available, you might receive the following prompt:

Spool files prompt

```
hh:mm:ss HCPWRS2513I
hh:mm:ss HCPWRS2513I Spool files on offline volumes      {nnnn|NONE}
hh:mm:ss HCPWRS2513I Spool files with I/O errors        {nnnn|NONE}
hh:mm:ss HCPWRS2513I Spool files with control errors    {nnnn|NONE}
hh:mm:ss HCPWRS2513I Spool files to be discarded        {nnnn|NONE}
hh:mm:ss HCPWRS2513I                                     -----
hh:mm:ss HCPWRS2513I Total files to be deleted          nnnn
hh:mm:ss HCPWRS2511A
hh:mm:ss HCPWRS2511A Spool files will be deleted because of
                   COLD start.
hh:mm:ss HCPWRS2511A No files have been deleted yet.

hh:mm:ss HCPWRS2511A To continue COLD start and delete files,
                   enter GO.
hh:mm:ss HCPWRS2511A To stop COLD start without deleting
                   files, enter STOP.
```

go

The system gives you an opportunity to stop the cold start and save your spool files. You do not need to save any spool files at this time; answer GO.

```

hh:mm:ss HCPWRS2512I Spooling initialization is complete.
hh:mm:ss DASD nnnn dump unit CP IPL pages nnnn
hh:mm:ss HCPAAU2700I System gateway ZVMV6R10 identified.
hh:mm:ss z/VM Version 6 Release 1.0, Service Level 0000 (64-bit),
built on IBM Virtualization Technology
hh:mm:ss There is no logmsg data
hh:mm:ss FILES: NO RDR, NO PRT, NO PUN
hh:mm:ss LOGON AT hh:mm:ss EDT DAY mm/dd/yy
hh:mm:ss GRAF nnnn LOGON AS OPERATOR USERS = n
hh:mm:ss HCPIOP952I nnnnM system storage
hh:mm:ss FILES: nnnnnnnn RDR, nnnnnnnn PRT, NO PUN
hh:mm:ss HCPCRC8082I Accounting records are accumulating for userid DISKACNT.

```

4. Disconnect from the OPERATOR user ID.

```

disconnect
DISCONNECT AT hh:mm:ss {EST|EDT} weekday mm/dd/yy

```

Press enter or clear key to continue

ENTER

5. Log on as MAINT.

ENTER

The default password for MAINT is MAINT.

logon maint

```

HCPLNM102E 080D DASD force R/O; R/W by operator
HCPLNM101E 080E DASD force R/O; R/O by operator
z/VM Version 6 Release 1.0, Service Level 0000 (64-bit),
built on IBM Virtualization Technology
There is no logmsg data
FILES: nnnn RDR, NO PRT, NO PUN
LOGON AT hh:mm:ss EDT DAY mm/dd/yy

```

z/VM V6.1.0 yyy-mm-dd hh:mm

ENTER

Ready; T=n.nn/n.nn hh:mm:ss

Step 6. Run INSTVM

In this step, you will:

- Run INSTVM with the DVD option to complete installation tasks.

Note: Running the INSTVM requires a full screen terminal with at least 20 lines.

1. IPL CMS to verify the CMS saved system is available.

```
ipl cms
z/VM V6.1.0   yyyy-mm-dd hh:mm
```

ENTER

```
Ready; T=n.nn/n.nn hh:mm:ss
```

Note: If the CMS saved system does not exist, there is a problem with spool space, resolve the problem before you attempt to continue.

2. Run INSTVM to complete the installation of z/VM from DVD.

```
instvm dvd
**** NOW EXECUTING INSTVM EXEC ON date AT time ****
HCPPLD8338I NOW EXECUTING ALLOCATION OF SYSTEM RESIDENCE PACK
HCPPLD8338I NOW EXECUTING UPDATE OF $MOVE$ $FILE$ C
HCPPLD8341I POSTLOAD FUNCTION "INSTALLATION CLEANUP" COMPLETED SUCCESSFULLY
HCPPLD8338I NOW EXECUTING DIRECTORY CLEANUP
HCPPLD8341I POSTLOAD FUNCTION "DIRECTORY CLEANUP AND ADD HELP DISK LINKS" COMPLETED SUCCESSFULLY
HCPPLD8338I NOW EXECUTING THE DIRECTXA COMMAND TO BRING THE UPDATED USER DIRECTORY ONLINE
HCPPLD8341I POSTLOAD FUNCTION "BRING UPDATED DIRECTORY ONLINE" COMPLETED SUCCESSFULLY

HCPPLD8392I POSTLOAD EXEC ENDED SUCCESSFULLY
DMSACC724I 2CC replaces C (2CC)
HCPIDV8493I ISSUING XAUTOLOG FOR VMSERVU
AUTO LOGON ***          VMSERVU  USERS = n
HCPCLS6056I XAUTOLOG information for VMSERVU: The IPL command is verified by the IPL
command processor.
VMSERVU : z/VM V6.1.0   yyyy-mm-dd hh:mm
VMSERVU : DMSACP723I B (193) R/O
VMSERVU : DMSWV1117I FILESERV processing begun at hh:mm:ss on dd month yyyy
VMSERVU : DMSWV1121I VMSERVU DMSPARMS A1 will be used for FILESERV processing
VMSERVU : DMSWV1121I VMSYSU POOLDEF A1 will be used for FILESERV processing
VMSERVU : DMS5BB3045I Ready for operator communications
HCPIDV8493I ISSUING XAUTOLOG FOR VMSERVR
AUTO LOGON ***          VMSERVR  USERS = n
HCPCLS6056I XAUTOLOG information for VMSERVR: The IPL command is verified by the IPL
command processor.
VMSERVR : z/VM V6.1.0   yyyy-mm-dd hh:mm
VMSERVR : DMSACP723I B (193) R/O
VMSERVR : DMSWV1117I FILESERV processing begun at hh:mm:ss on dd month yyyy
VMSERVR : DMSWV1121I VMSERVR DMSPARMS A1 will be used for FILESERV processing
VMSERVR : DMSWV1121I VMSYSR POOLDEF A1 will be used for FILESERV processing
VMSERVR : DMS6LG3335I CRR log recovery begins at mm-dd-yy hh:mm:ss
VMSERVR : DMS6LG3335I CRR log recovery completes at mm-dd-yy hh:mm:ss
VMSERVR : DMS5BB3045I Ready for operator communications
```

Extra messages received if all products were loaded to minidisks

```

DASD 0804 DETACHED
HCPIDV8493I ISSUING XAUTOLOG FOR VMSERVS
AUTO LOGON ***          VMSERVS USERS = n
HCPCLS6056I XAUTOLOG information for VMSERVS: The IPL command is verified by the IPL
command processor.
VMSERVS : z/VM V6.1.0    yyyy-mm-dd hh:mm
VMSERVS : DMSACP723I B (193) R/O
VMSERVS : DMSWFV1117I FILESERV processing begun at hh:mm:ss on dd month yyyy
VMSERVS : DMSWFV1121I VMSERVS DMSPARMS A1 will be used for FILESERV processing
VMSERVS : DMS4PD3400I Initializing begins for DDNAME = CONTROL
VMSERVS : DMS4PD3400I Initializing ends for DDNAME = CONTROL
VMSERVS : DMS4PD3400I Initializing begins for DDNAME = MDK00001
VMSERVS : DMS4PD3400I Initializing ends for DDNAME = MDK00001
VMSERVS : DMS4PD3400I Initializing begins for DDNAME = MDK00002
VMSERVS : DMS4PD3400I Initializing ends for DDNAME = MDK00002
VMSERVS : DMS4PD3400I Initializing begins for DDNAME = LOG1
VMSERVS : DMS4PD3400I Initializing ends for DDNAME = LOG1
VMSERVS : DMS4PD3400I Initializing begins for DDNAME = LOG2
VMSERVS : DMS4PD3400I Initializing ends for DDNAME = LOG2
VMSERVS : DMS5FD3032I File pool server has terminated
VMSERVS : DMSWFV1120I File VMSYS POOLDEF A1 created or replaced
VMSERVS : DMSWFV1117I FILESERV processing ended at hh:mm:ss on dd month yyyy
RDR FILE nnnn SENT FROM VMSERVS PUN WAS nnnn RECS nnnn CPY 001 A NOHOLD NOKEEP
VMSERVS : File FILESERV VALID A3 sent to MAINT at ZVMV6R10 on mm/dd/yy hh:mm:ss
VMSERVS : Ready; T=n.nn/n.nn hh:mm:ss

HCPQCS150A User VMSERVS has issued a VM read
VMSERVS : CONNECT= nn:nn:nn VIRTCPU= nnn:nn.nn TOTCPU= nnn:nn.nn
VMSERVS : LOGOFF AT hh:mm:ss timezone day mm/dd/yy BY MAINT
USER DSC LOGOFF AS VMSERVS USERS = 2    FORCED BY MAINT
DASD 0804 DETACHED

```

```

HCPIDV8493I ISSUING XAUTOLOG FOR VMSERVS
AUTO LOGON ***          VMSERVS USERS = n
HCPCLS6056I XAUTOLOG information for VMSERVS: The IPL command is verified by the IPL
command processor.
VMSERVS : z/VM V6.1.0    yyyy-mm-dd hh:mm
VMSERVS : DMSACP723I B (193) R/O
VMSERVS : DMSWFV1117I FILESERV processing begun at hh:mm:ss on dd month yyyy
VMSERVS : DMSWFV1121I VMSERVS DMSPARMS A1 will be used for FILESERV processing
VMSERVS : DMSWFV1121I VMSYS POOLDEF A1 will be used for FILESERV processing
VMSERVS : DMS5BB3045I Ready for operator communications

```

You might not receive one or more of the following messages

```

HCPIDV8338I UPDATING SYSTEM TABLES AND CLEANING UP FILEPOOL DIRECTORIES
RC=0 from EXEC OPENVM UNMOUNT /
RC=0 from EXEC OPENVM UNMOUNT /
RC=0 from EXEC OPENVM UNMOUNT /
RC=0 from EXEC OPENVM UNMOUNT /
RC=0 from EXEC OPENVM UNMOUNT /

```

```

HCPIFP8392I INSTPOOL EXEC ENDED SUCCESSFULLY
HCPIVM8392I INSTVM EXEC ENDED SUCCESSFULLY
Ready; T=n.nn/n.nn hh:mm:ss

```

Run INSTVM

After this point, when you IPL the system, you should use the default IPL parameters and should no longer use COLD DRAIN NOAUTOLOG.

Step 7. Run SERVICE

In this step, you will:

- Load the service files from the recommended service upgrade (RSU) servlink.

1. Log on as MAINT.

```

ENTER
logon maint
:
Ready; T=n.nn/n.nn hh:mm:ss

```

The default password for MAINT is MAINT.

2. Make sure the file pool is available.

If you receive message DMS1153E, indicating the MAINT file pool is unavailable or unknown, you need to XAUTOLOG VMSESRVS, VMSESRVU, and VMSESRVR.

```

query limits all
Userid  Storage Group  4K Block Limit  4K Blocks Committed  Threshold
userid1      2              n              n-nn%             nn%
userid2      2              n              n-nn%             nn%
:
Ready; T=n.nn/n.nn hh:mm:ss

```

3. IPL CMS.

```

ipl cms
z/VM V6.1.0   yyyy-mm-dd hh:mm

```

```

ENTER
Ready; T=n.nn/n.nn hh:mm:ss

```

4. Access the disk containing the RSU servlink as C.

```

access 500 c
DMSACC724I 500 replaces C (2CC)
Ready;

```

5. Get the file names of the RSU envelopes on the 500 disk.

```

listfile * servlink c
610xRSUn servlink c
610xRSUn servlink c

```

x RSU number.
n Volume number.

6. Run SERVICE.

```

service all envfn1 envfn2 ...
VMFSRV2760I SERVICE processing started
:
VMFSRV2760I SERVICE processing completed
successfully
Ready; T=n.nn/n.nn hh:mm:ss

```

envfn1
 File name for the first envelope 610xRSU1.
envfn2 ...
 File name for the second envelope 610xRSU2,
 and so on.

7. View the SERVICE messages log (VMFVIEW SERVICE) and handle any nonzero return code, if necessary. Base your action on the following table.

Run SERVICE

If you received . . .	Then . . .
Return code 4	<ol style="list-style-type: none">1. Issue VMFVIEW SERVICE.2. Ignore any warning messages listed in the note below. Take appropriate actions based on other warning messages you receive.3. Go to “Step 8. Run PUT2PROD” on page 87.
A return code greater than 4	<ol style="list-style-type: none">1. Issue VMFVIEW SERVICE and check for warning and error messages.2. Ignore any warning messages listed in the note below. Take appropriate actions based on other warning messages you receive.3. Correct all errors reported in the error messages.4. Restart by issuing the SERVICE command as displayed in the message VMFSRV2310W.5. If you receive a nonzero return code, repeat substep 7 on page 85.6. Go to “Step 8. Run PUT2PROD” on page 87.

Note: You can ignore the following messages and their associated VMF1966W message.

- DMSLI0201W The following names are undefined: ISPLINK ARIPRDI
- DMSLI0201W The following names are undefined: DMSDSCSC
- DMSLI0201W The following names are undefined: DMSUSRX1 DMSUSRX2
- DMSLI0202W Duplicate identifier (Associated with object IOACMAIN MODULE.)
- DMSLKD004W Warning messages issued (Associated with objects ILBONBL, ILBONTR, ILBOREC, ILBORNT, ILBOSND, ILBOSNT, and ILBOSSN.)
- VMFSRV1221W The Stand Alone Dump Utility must be rebuilt.

8. Use the VMFUPDAT SYSMEMO command to review any memos that were received with this service.

Step 8. Run PUT2PROD

In this step, you will:

- Run PUT2PROD to place the product into production.

1. Log on as MAINT.

```

ENTER
logon maint
:
Ready; T=n.nn/n.nn hh:mm:ss

```

The default password for MAINT is MAINT.

2. Make sure the file pool is available.

If you receive message DMS1153E, indicating the MAINT file pool is unavailable or unknown, you need to XAUTOLOG VMSEVS, VMSERVU, and VMSERVR.

```

query limits all
Userid  Storage Group 4K Block Limit 4K Blocks Committed Threshold
userid1      2          n          n-nn%      nn%
userid2      2          n          n-nn%      nn%
:
Ready; T=n.nn/n.nn hh:mm:ss

```

3. IPL CMS and access the VMSES/E test build disk.

```

ipl cms
z/VM V6.1.0   yyyy-mm-dd hh:mm

```

```

ENTER
Ready; T=n.nn/n.nn hh:mm:ss

```

```

access 5E6 B
Ready; T=n.nn/n.nn hh:mm:ss

```

4. Run PUT2PROD.

```

put2prod
VMFP2P2760I PUT2PROD processing started
:
VMFP2P2760I PUT2PROD processing completed successfully
Ready; T=n.nn/n.nn hh:mm:ss

```

5. Handle a nonzero return code. Base your action on the following table.

If you received . . .	Then . . .
Return code 4	<ol style="list-style-type: none"> Issue VMFVIEW PUT2PROD. Ignore any warning messages listed in the note below. Take appropriate actions based on other warning messages you receive.

Run PUT2PROD

If you received . . .	Then . . .
A return code greater than 4	<ol style="list-style-type: none"><li data-bbox="568 210 1421 241">1. Issue VMFVIEW PUT2PROD and check for warning and error messages.<li data-bbox="568 241 1421 315">2. Ignore any warning messages listed in the note below in this table. Take appropriate actions based on other warning messages you receive.<li data-bbox="568 315 1421 346">3. Correct all errors reported in the error messages.<li data-bbox="568 346 1421 378">4. Issue IPL CMS.<li data-bbox="568 378 1421 409">5. Issue PUT2PROD.<li data-bbox="568 409 1421 468">6. If you receive a nonzero return code, repeat substep 5 on page 87.

Note: You can ignore the following messages.

- DMSDCS1083E Saved segment \$\$DMY\$\$ does not exist
- DMSWLG292W Text data will be loaded at '20000'x in user area; user data may be overwritten.
- DTCPRD3043W File *fn ft fm* has been updated; It's contents should be reviewed for changes that may affect your use of this file.
- TCPMSM0002W File TCPIP DATA cannot be located
- TCPMSM0002W TCP/IP appears not to have been configured

Step 9. Shut Down and Re-IPL the System

In this step, you will:

- Shut down the V6.1 system.
- IPL the V6.1 system using the new CP nucleus.

1. Shut down and re-IPL the V6.1 system.

shutdown reipl

SYSTEM SHUTDOWN STARTED
Ready; T=*n.nn/n.nn hh:mm:ss*

The shut down message is displayed on all enabled consoles.

The real system console shows disabled PSW wait state.

HCPWRP963I STARTING SHUTDOWN STEP . . .
:
:
HCPWRP962I VM SHUTDOWN COMPLETED IN *n* SEC
HCPWRP9277I SYSTEM TERMINATION COMPLETE,
ATTEMPTING RESTART

HCP963I, HCP962I, and HCP9277I will appear on the operator's console.

hh:mm:ss HCPWRP9277I SYSTEM TERMINATION COMPLETE.
ATTEMPTING RESTART

hh:mm:ss z/VM SYSTEM RESTART FROM SHUTDOWN REIPL

hh:mm:ss z/VM V6 R1.0
SERVICE LEVEL *nnnn* (64-BIT)

hh:mm:ss SYSTEM NUCLEUS CREATED ON *yyyy-mm-dd* AT *hh:mm:ss*,
LOADED FROM 610RES

hh:mm:ss *****

hh:mm:ss * LICENSED MATERIALS - PROPERTY OF IBM* *

hh:mm:ss * 5741-A07 (C) COPYRIGHT IBM CORP. 1983, *

hh:mm:ss * 2009. ALL RIGHTS RESERVED. *

hh:mm:ss * US GOVERNMENT USERS RESTRICTED RIGHTS - *

hh:mm:ss * USE, DUPLICATION OR DISCLOSURE *

hh:mm:ss * RESTRICTED BY GSA ADP SCHEDULE CONTRACT *

hh:mm:ss * WITH IBM CORP. *

hh:mm:ss * *

hh:mm:ss * * TRADEMARK OF INTERNATIONAL BUSINESS *

hh:mm:ss * MACHINES *

hh:mm:ss *****

hh:mm:ss HCPZC06718I Using parm disk 1 on volume *valid* (device *xxxx*).

hh:mm:ss HCPZC06718I Parm disk resides on cylinders *xx* through *xx*.

:

Note: If you receive informational message HCPIS954I for your 610RES volume (for example, DASD 505A VOLID 610RES IS A DUPLICATE OF DASD 5516), you can ignore this message and proceed. For any other occurrence of HCPIS954I, you have duplicate DASD with the same label and must correct this error before continuing.

hh:mm:ss The directory on volume 610RES at address *nnnn*
has been brought online.

hh:mm:ss HCPWRS2513I

hh:mm:ss HCPWRS2513I Spool files available {*nnnn*|none}

hh:mm:ss HCPWRS2512I Spooling initialization is complete.

:

hh:mm:ss FILES: *nnn* RDR, *nnn* PRT, *nnn* PUN

hh:mm:ss LOGON AT *hh:mm:ss* {EST|EDT} *weekday mm/dd/yy*

:

hh:mm:ss HCPiop952I *nnnnM* system storage

hh:mm:ss FILES: *nnnnnnn* RDR, *nnnnnnn* PRT, NO PUN

Shut Down and Re-IPL the System

Message HCP952I tells you the amount of storage available.

The FILES message refers to operator spool files.

CP automatically disconnects from the primary system operator user ID (OPERATOR).

```
hh:mm:ss HCPUS0967I Disconnect OPERATOR - system
          restarted SHUTDOWN and system console
          not VM operator console
hh:mm:ss HCP952I Accounting records are accumulating for userid DISKACNT
hh:mm:ss DISCONNECT AT hh:mm:ss {EST|EDT} weekday mm/dd/yy
hh:mm:ss Press enter or clear key to continue
```

ENTER

Press Enter or the Clear key to continue.

2. Log on as MAINT.

ENTER

The password for MAINT is MAINT.

```
logon maint
:
Ready; T=n.nn/n.nn hh:mm:ss
```

What to do next

See Part 3, "Post z/VM System Installation," on page 129.

Chapter 6. Second-Level DVD Installation Method

In this chapter, you will:

- Set up the user ID for installation.
- Run the DVDPRIME EXEC.

Base your choice on which source you will use to perform a second-level installation.

If you chose to install from a . . .	Then see . . .
DVD drive	"From a DVD Drive" on page 92
FTP server directory	"From an FTP Server Directory" on page 96
VM minidisk	"From a VM Minidisk" on page 100

From a DVD Drive

Step 1. Set up the User ID for Installation

In this step, you will

- Complete the installation worksheet.
- Load the z/VM system DVD in the DVD drive.
- Log on to your first-level user ID.

1. Complete the installation worksheet (Table 8 on page 64) in Chapter 4, “Plan Your DVD Installation,” on page 59.
2. Load the z/VM system DVD in the DVD drive of the FTP server you are using for installation. Wait until the light on the DVD drive goes out or stops blinking to continue.
3. Log on to the first-level user ID that you will use to install V6.1.
4. Make sure your user ID meets the “second-level installation user ID requirements” on page 61.
5. Spool the console to make sure it is empty and started.

```
spool console close start *  
RDR FILE filenum SENT FROM userid CON WAS nnnn RECS nnnn CPY nnn T NOHOLD NOKEEP  
Ready;
```

6. Verify you have a 2222 read/write minidisk with exactly 5 cylinders if installing to 3390 or 7200 512-KB blocks if installing to FBA.

```
query v 2222  
DASD 2222 3390 xxxxxx R/W 5 CYL ON DASD nnnn SUBCHANNEL = nnnn  
Ready; T=n.nn/n.nn hh:mm:ss
```

7. Access the disk that contains INSTPIPE module. The INSTPIPE module is shipped on the MAINT 2CC minidisk.

```
access 2CC c  
Ready; T=n.nn/n.nn hh:mm:ss
```

8. Copy the files needed to run DVDPRIME from the DVD to the 2222 minidisk.

```
instpipe  
Ready; T=n.nn/n.nn hh:mm:ss  
pipe ftpget -h host -u userID -p password -d ftpdire/CPDVD  
-v BEF -DVDEOF -f ddd222* |UNPACK| restcmd 2222
```

From a DVD Drive - Setup the User ID for Installation

host

IP address or FTP host name.

userID

User ID used to log on to the FTP server.

password

Password for the user ID used to log on to the FTP server.

ftpd

Path to the DVD drive with /CPDVD appended to the end of the path.

ddd

CKD for 3390 or FBA for FBA. These must be entered in uppercase.

restcmd

ECKDREST for 3390 or MDREST for FBA.

Note: In the above PIPE command you may use a different stage separator by including the **stagesep** keyword. For example:

```
pipe ( stagesep ! ) ftpget -h host -u userID -p
password -d ftpdir/CPDVD -v BEF -DVDEOF -f
ddd222* !UNPACK! restcmd 2222
```

```
{FBA222* | CKD222*}
```

```
DMSRXS1408W File TCPIP DATA * not found
```

```
{MDREST|ECKDREST}: WROTE nnn {BLOCKS|TRACKS} ON 2222, RC=0
```

```
Ready; T=n.nn/n.nn hh:mm:ss
```

You might not receive this message.

From a DVD Drive - Run DVDPRIME

Step 2. Run DVDPRIME

In this step, you will:

- Run the DVDPRIME to load the 22CC and 2CF1 disks.

1. IPL CMS to remove the old INSTPIPE module from storage.

```
ipl cms
z/VM V6.1.0   yyyy-mm-dd hh:mm
```

ENTER

```
Ready; T=n.nn/n.nn hh:mm:ss
```

2. Access the 2222 disk as C.

```
access 2222 c
Ready; T=n.nn/n.nn hh:mm:ss
```

3. Verify the first occurrence of INSTPIPE MODULE is on disk C. Remove or rename all other copies.

```
listfile instpipe module *
INSTPIPE MODULE C1
Ready; T=n.nn/n.nn hh:mm:ss
```

4. Run DVDPRIME with the *dasdtype* you are using to install.

```
dvdprime dasdtype (dvd dasdtype
                                     3390 or FBA.
**** NOW EXECUTING DVDPRIME EXEC ON date AT time ****
```

5. Complete the DVDPRIME PANEL by filling in the information for your FTP server.

```
*** DVDPRIME PANEL ***

Enter information in empty fields and press PF5 to process.

HOSTNAME OR IP ADDRESS: _____
FTP USERID:             _____
FTP PASSWORD:           _____
DVD PATHNAME:           _____

PF1 = HELP   PF3/PF12 = QUIT   PF5 = Process   ENTER = Refresh
```

Figure 8. Installation Planning Panel

HOSTNAME OR IP ADDRESS:

This field should be filled in with the IP ADDRESS or HOSTNAME of your z/VM system. A host name must begin with a letter, and may contain only alphanumeric characters (A-Z,a-z,0-9) or hyphens (-). For example: **MyOrg-VM01**

Specify an IP address in dotted-decimal form for your IP version 4 interface. For example: **129.42.16.99**

FTP USERID:

User ID used to log on to the FTP server. Must be 40 or less alphanumeric characters.

FTP PASSWORD:

Password used to log on to the FTP server. Must be 40 or less alphanumeric characters.

DVD PATHNAME:

Enter the path to the DVD drive according to the conventions used by your server and append CPDVD to the end of your path. The maximum length is 40 characters. For example:

```
mydvddrive/CPDVD
cpdvd
e:/cpdvd
vmftpdir/CPDVD
```

6. Press F5 to process.

F5

```
HCPDVP8440I NOW LOADING 22CC DISK
{FBA222* | CKD222*}
DMSRXS1408W File TCPIP DATA * not found           You might not receive this message.

{MDREST|ECKDREST}: WROTE nnnn {BLOCKS|TRACKS} ON 22CC, RC=0

HCPDVP8440I NOW LOADING 2CF1 DISK
{FBACF1* | CKDCF1*}
DMSRXS1408W File TCPIP DATA * not found           You might not receive this message.

PROCESSING {FBACF100 | CKDCF100}
:
PROCESSING {FBACF10n | CKDCF10n}
{MDREST|ECKDREST}: WROTE nnnn {BLOCKS|TRACKS} ON 2CF1, RC=0

HCPDVP8392I DVDPRIME EXEC ENDED SUCCESSFULLY
Ready; T=n.nn/n.nn hh:mm:ss
```

What to do next

See Chapter 7, "Load the System Image," on page 107.

From an FTP Server Directory

Step 1. Set up the User ID for Installation

In this step, you will

- Complete the installation worksheet.
- Upload the contents of the z/VM system DVD and the RSU DVD to an FTP server directory.
- Log on to your first-level user ID.

1. Complete the installation worksheet (Table 8 on page 64) in Chapter 4, “Plan Your DVD Installation,” on page 59.
2. Upload the contents of the DVD to the FTP server directory.
 - a. Create a new directory on the FTP server. The maximum length of the directory path name is 40 characters. The FTP server will need at least 3 GB of free space.
 - b. Upload the contents of each DVD to the directory. After the contents of the z/VM system DVD have been uploaded, upload the contents of the RSU DVD to the same directory, overwriting any duplicate files.
3. Log on to the first-level user ID that you will use to install V6.1.
4. Make sure your user ID meets the “second-level installation user ID requirements” on page 61.
5. Spool the console to make sure it is empty and started.

```
spool console close start *
RDR FILE filenum SENT FROM userid CON WAS nnnn RECS nnnn CPY nnn T NOHOLD NOKEEP
Ready;
```

6. Verify you have a 2222 read/write minidisk with exactly 5 cylinders if installing to 3390 or 7200 512-KB blocks if installing to FBA.

```
query v 2222
DASD 2222 3390 xxxxxx R/W      5 CYL ON DASD nnnn SUBCHANNEL = nnnn
Ready; T=n.nn/n.nn hh:mm:ss
```

7. Access the disk that contains INSTPIPE module. The INSTPIPE module is shipped on the MAINT 2CC minidisk.

```
access 2CC c
Ready; T=n.nn/n.nn hh:mm:ss
```

8. Copy the files needed to run DVDPRIME from the FTP server to the 2222 minidisk.

```
instpipe
Ready; T=n.nn/n.nn hh:mm:ss
pipe ftpget -h host -u userID -p password -d ftpdir
-v BEF -DVDEOF -f ddd222* |UNPACK| restcmd 2222
```

From an FTP Server Directory - Set up the User ID for Installation

host

IP address or FTP host name.

userID

User ID used to log on to the FTP server.

password

Password for the user ID used to log on to the FTP server.

ftpd

Path to the FTP server directory.

ddd

CKD for 3390 or FBA for FBA. These must be entered in uppercase.

restcmd

ECKDREST for 3390 or MDREST for FBA.

Note: In the above PIPE command you may use a different stage separator by including the **stagesep** keyword. For example:

```
pipe ( stagesep ! ) ftpget -h host -u userID -p  
password -d ftpdir -v BEF -DVDEOF -f ddd222*  
!UNPACK! restcmd 2222
```

```
{FBA222* | CKD222*}
```

```
DMSRXS1408W File TCP/IP DATA * not found
```

```
{MDREST|ECKDREST}: WROTE nnn {BLOCKS|TRACKS} ON 2222, RC=0
```

```
Ready; T=n.nn/n.nn hh:mm:ss
```

You might not receive this message.

From an FTP Server Directory - Run DVDPRIME

Step 2. Run DVDPRIME

In this step, you will:

- Run the DVDPRIME to load the 22CC and 2CF1 disks.

1. IPL CMS to remove the old INSTPIPE module from storage.

```
ipl cms
z/VM V6.1.0   yyyy-mm-dd hh:mm
```

ENTER

```
Ready; T=n.nn/n.nn hh:mm:ss
```

2. Access the 2222 disk as C.

```
access 2222 c
Ready; T=n.nn/n.nn hh:mm:ss
```

3. Verify the first occurrence of INSTPIPE MODULE is on disk C. Remove or rename all other copies.

```
listfile instpipe module *
INSTPIPE MODULE C1
Ready; T=n.nn/n.nn hh:mm:ss
```

4. Run DVDPRIME with the *dasdtype* you are using to install.

```
dvdprime dasdtype (server dasdtype
                                     3390 or FBA.
**** NOW EXECUTING DVDPRIME EXEC ON date AT time ****
```

5. Complete the DVDPRIME panel by filling in the information for your FTP server.

```
*** DVDPRIME PANEL ***

Enter information in empty fields and press PF5 to process.

HOSTNAME OR IP ADDRESS: _____
FTP USERID:             _____
FTP PASSWORD:           _____
DVD PATHNAME:           _____

PF1 = HELP   PF3/PF12 = QUIT   PF5 = Process   ENTER = Refresh
```

Figure 9. DVDPRIME Panel

HOSTNAME OR IP ADDRESS:

This field should be filled in with the IP ADDRESS or HOSTNAME of your z/VM system. A host name must begin with a letter, and may contain only alphanumeric characters (A-Z,a-z,0-9) or hyphens (-). For example: **MyOrg-VM01**

Specify an IP address in dotted-decimal form for your IP version 4 interface. For example: **129.42.16.99**

FTP USERID:

From an FTP Server Directory - Run DVDPRIME

User ID used to log on to the FTP server. Must be 40 or less alphanumeric characters.

FTP PASSWORD:

Password used to log on to the FTP server. Must be 40 or less alphanumeric characters.

DVD PATHNAME:

Enter the path to the FTP server directory according to the conventions used by your server. The maximum length is 40 characters. For example:

```
mydvddrive/ftpdir
e:/dirname
vmftpdir
```

6. Press F5 to process.

F5

```
HCPDVP8440I NOW LOADING 22CC DISK
{FBA222* | CKD222*}
DMSRXS1408W File TCPIP DATA * not found           You might not receive this message

{MDREST|ECKDREST}: WROTE nnnn {BLOCKS|TRACKS} ON 22CC, RC=0

HCPDVP8440I NOW LOADING 2CF1 DISK
{FBACF1* | CKDCF1*}
DMSRXS1408W File TCPIP DATA * not found           You might not receive this message.

PROCESSING {FBACF100 | CKDCF100}
:
PROCESSING {FBACF10n | CKDCF10n}
{MDREST|ECKDREST}: WROTE nnnn {BLOCKS|TRACKS} ON 2CF1, RC=0

HCPDVP8392I DVDPRIME EXEC ENDED SUCCESSFULLY
Ready; T=n.nn/n.nn hh:mm:ss
```

What to do next

See Chapter 7, "Load the System Image," on page 107.

From a VM Minidisk

Step 1. Set up the User ID for Installation

In this step, you will

- Complete the installation worksheet.
- Log on to your first-level user ID.
- Copy the contents of the z/VM system DVD and the RSU DVD to a VM minidisk.
- Restore the DVDPRIME files to the 2222 minidisk.

1. Complete the installation worksheet (Table 8 on page 64) in Chapter 4, “Plan Your DVD Installation,” on page 59.
2. Log on to the first-level user ID that you will use for installation.
3. Make sure your user ID meets the “second-level installation user ID requirements” on page 61.
4. Link to the minidisk to be used to contain the image files.
5. Access the minidisk address as W.

```
access diskaddr w  
Ready; T=n.nn/n.nn hh:mm:ss
```

```
diskaddr  
Address of the CMS-formatted minidisk where  
the DVD files are to be copied.
```

6. Copy the contents of the z/VM system DVD to a VM minidisk accessed as W. The minidisk needs to have the equivalent of at least 4500 cylinders of available 3390 DASD. The minidisk must not contain any other IMAGE files.

Note: If you have an FTP server with access to a DVD drive, continue with this substep. If you do not have an FTP server with access to a DVD drive, use the upload function of your terminal emulator to copy the contents of the z/VM system DVD and the RSU DVD to the minidisk. See Appendix J, “Using a Terminal Emulator to Upload Files from a DVD,” on page 219. After uploading the files using your terminal emulator, continue with substep 9 on page 103.

- a. Load the z/VM system DVD in the DVD drive of the FTP server you are using for installation. Wait until the light on the DVD drive goes out or stops blinking before continuing.
- b. Access the TCPIP client code disk.

```
link tcpmaint 592 592 rr  
Ready; T=n.nn/n.nn hh:mm:ss
```

```
access 592 z  
Ready; T=n.nn/n.nn hh:mm:ss
```

- C. Copy the files from the z/VM system DVD.

```
terminal more 1 1  
Ready;
```

```
ftp  
VM TCP/IP FTP Level nnn  
OPEN (name of foreign host):
```

From a VM Minidisk - Set up the User ID for Installation

```
host
Connecting to host
220 FTP Server ready...
USER (identify yourself to the host):
userID
```

```
>>>USER userID
331 User name okay, need password.
Password:
password

>>>PASS *****
230 User logged in, proceed
Command:
cd ftpdir/CPDVD
```

```
>>>CWD ftpdir/CPDVD
250 Directory changed to ftpdir/CPDVD
Command:
lcd w
```

Local directory mode is 'W'

```
Command:
binary f 1028
>>>TYPE i
200 Type set to I.
Command:
mget ddd*
```

```
>>>TYPE a
200 Type set to A
>>>PORThost
200 PORT Command successful.
>>>NLST ddd*
150 Opening ASCII mode data connection for /bin/ls.
226 Transfer complete.
>>>TYPE i
200 Type set to I.
```

```
host
IP address or FTP host name.
```

```
userID
User ID used to log on to the FTP server.
```

```
password
Password for the user ID used to log on to the
FTP server.
```

```
ftpdir
Path to the DVD drive with /CPDVD appended to
the end of the path. For example, e:/CPDVD.
```

```
ddd
CKD for 3390 or FBA for FBA. These must be
entered in uppercase.
```

The following is repeated for each file transferred

```
>>>PORT host
200 PORT Command successful.
>>>RETR dddnnnnn
150 Opening BINARY mode data connection for dddnnnnn (nnnnnnn Bytes).
nnnnnnn bytes transferred.
226 Transfer complete.
nnnnnnn bytes transferred in nn.nnn seconds. Transfer rate nnn.nn Kbytes/sec.
```

```
Command:
quit
>>>QUIT
221 Goodbye!
Ready;
```

From a VM Minidisk - Set up the User ID for Installation

7. If you used your terminal emulator to upload the contents of the RSU DVD, skip to substep 9 on page 103. Otherwise, copy the contents of the RSU DVD to the same VM minidisk used for the z/VM system DVD.
 - a. Load the RSU DVD in the DVD drive of the FTP server you are using for installation. Wait until the light on the DVD drive goes out or stop blinking before continuing.
 - b. Copy the RSU files from the DVD.

ftp

VM TCP/IP FTP Level *nnn*

OPEN (name of foreign host):

host

Connecting to *host*

220 FTP Server ready...

USER (identify yourself to the host):

userID

>>>USER *userID*

331 User name okay, need password.

Password:

password

>>>PASS *****

230 User logged in, proceed.

Command:

cd *ftpdir/CPDVD*

>>>CWD *ftpdir/CPDVD*

250 Directory changed to *ftpdir/CPDVD*

Command:

lcd w

Local directory mode is 'W'

Command:

binary f 1028

>>>TYPE i

200 Type set to I.

Command:

mget *ddd** (**replace**

>>>TYPE a

200 Type set to A

>>>PORT *host*

200 PORT Command successful.

>>>NLST *ddd**

150 Opening ASCII mode data connection for /bin/l~~s~~.

226 Transfer complete.

>>>TYPE i

200 Type set to I.

host

IP address or FTP host name.

userID

User ID used to log on to the FTP server.

password

Password for the user ID used to log on to the FTP server.

ftpdir

Path to the DVD drive with /CPDVD appended to the end of the path. For example, e:/CPDVD.

ddd

CKD for 3390 or FBA for FBA. These must be entered in uppercase.

The following is repeated for each file transferred

```
>>>PORT host
200 PORT Command successful.
>>>RETR dddnnnnn
150 Opening BINARY mode data connection for dddnnnnn (nnnnnnn Bytes).
nnnnnnn bytes transferred.
226 Transfer complete.
nnnnnnn bytes transferred in nn.nnn seconds. Transfer rate nnn.nn Kbytes/sec.
```

```
Command:
quit
>>>QUIT
221 Goodbye!
Ready;
```

8. The MGET command copied the files with a file type of \$DEFAULT. The file type needs to be renamed to IMAGE.

```
terminal more 50 10
Ready;

rename * $default w = image =
Ready;
```

9. Spool the console to make sure it is empty and started.

```
spool console close start *
RDR FILE filenum SENT FROM userid CON WAS nnnn RECS nnnn CPY nnn T NOHOLD NOKEEP
Ready;
```

10. Access the disk that contains INSTPIPE module. The INSTPIPE module is shipped on the MAINT 2CC minidisk.

```
access 2CC c
Ready; T=n.nn/n.nn hh:mm:ss
```

11. Verify you have a 2222 read/write minidisk of exactly 5 cylinders if installing to 3390 or 7200 512-KB blocks if installing to FBA .

```
query v 2222
DASD 2222 3390 xxxxxx R/W 5 CYL ON DASD nnnn SUBCHANNEL = nnnn
Ready; T=n.nn/n.nn hh:mm:ss
```

12. Verify the image file has a **fixed (F)** file format and a logical record length (LRECL) of **1028**. If the file format or logical record length is incorrect, the image file was copied incorrectly. Erase the image file off the minidisk and copy the image file again using the correct parameters. Repeat the process starting with substep 6 on page 100.

```
listfile *222* image w (alloc
FILENAME FILETYPE FM FORMAT LRECL RECS BLOCKS
xxx22200 IMAGE W1 F 1028 xxxx xxxx
Ready; T=n.nn/n.nn hh:mm:ss
```

From a VM Minidisk - Set up the User ID for Installation

13. Restore the files needed to run DVDPRIME to the 2222 minidisk.

instpipe

Ready; T=*n.nn/n.nn hh:mm:ss*

pipe dvddecod *ddd222* image w |UNPACK| restcmd 2222

INVALID INPUT - RECORD LENGTH ERROR AT RECORD COUNT
{MDREST|ECKDREST}: WROTE *nnn* {BLOCKS|TRACKS} ON 2222, RC=0
Ready (00008); T=*n.nn/n.nn hh:mm:ss*

ddd

CKD for 3390 or FBA for FBA. These must be entered in uppercase.

restcmd

ECKDREST for 3390 or MDREST for FBA.

Note: In the above PIPE command you may use a different stage separator by including the **stagesep** keyword. For example:

pipe (stagesep !) dvddecod *ddd222* image w !UNPACK! restcmd 2222

Step 2. Run DVDPRIME

In this step, you will:

- Run the DVDPRIME to load the 22CC and 2CF1 disks.

1. IPL CMS to remove the old INSTPIPE module from storage.

```
ipl cms
z/VM V6.1.0   yyyy-mm-dd hh:mm
```

ENTER

```
Ready; T=n.nn/n.nn hh:mm:ss
```

2. Access the minidisk address that contains the image files as W.

```
access diskaddr w
Ready; T=n.nn/n.nn hh:mm:ss
```

diskaddr

Address of the minidisk where the DVD image files were copied.

3. Access the 2222 disk as C.

```
access 2222 c
Ready; T=n.nn/n.nn hh:mm:ss
```

4. Verify the first occurrence of INSTPIPE MODULE is on disk C. Remove or rename all other copies.

```
listfile instpipe module *
INSTPIPE MODULE C1
Ready; T=n.nn/n.nn hh:mm:ss
```

5. Run DVDPRIME with the *dasdtype* you are using to install.

```
dvdprime dasdtype (disk
```

dasdtype

3390 or FBA.

```
**** NOW EXECUTING DVDPRIME EXEC ON date AT time ****
HCPDVP8440I NOW LOADING 22CC DISK
DMSRXS1408W File TCPIP DATA * not found      You might not receive this message.
{MDREST|ECKDREST}: WROTE nnnn {BLOCKS|TRACKS} ON 22CC, RC=0
HCPDVP8440I NOW LOADING 2CF1 DISK
DMSRXS1408W File TCPIP DATA * not found      You might not receive this message.
{MDREST|ECKDREST}: WROTE nnnn {BLOCKS|TRACKS} ON 2CF1, RC=0
HCPDVP8392I DVDPRIME EXEC ENDED SUCCESSFULLY
Ready; T=n.nn/n.nn hh:mm:ss
```

What to do next

See Chapter 7, "Load the System Image," on page 107.

From a VM Minidisk - Run DVDPRIME EXEC

Chapter 7. Load the System Image

In this chapter, you will:

- Use INSTPLAN to enter your installation plan.
- Use INSTDVD to load the system image and RSU image files.
- IPL your new system.
- Use INSTVM to finish the install of z/VM.
- Use SERVICE and PUT2PROD to install RSU service.
- Configure TCP/IP (optional).
- Load the new CPLOAD module.
- Back up the z/VM system to tape or DASD.

Step 1. Run INSTPLAN

In this step, you will:

- Run INSTPLAN.

1. Access the minidisk with the new install code and run INSTPLAN.

```
access 22CC c
```

```
Ready;
```

```
instplan
```

```
**** NOW EXECUTING INSTPLAN EXEC ON date AT time ****
```

```
*** z/VM INSTALLATION PLANNING ***
```

Mark the product(s) selected to be installed into the VMSYS filepool with an "F" and those selected to be installed to minidisks with an "M"

Install To	Product	Install To	Product	Install To	Product
M	VM	M	OSA	M	PERFTK
M	VMHCD	M	RACF	M	DIRM
M	RSCS	M	ICKDSF	M	TCPIP

Place a nonblank character in front of the System Default Language you would like for your system.

```
_ AMENG      _ UCENG      _ KANJI
```

Place a nonblank character in front of the DASD model onto which your z/VM system will be loaded. Only one model may be selected.

```
_ 3390 Mod 3      _ 3390 Mod 9      _ FBA DASD 3.5
```

```
PF1 = HELP  PF3/PF12 = QUIT  PF5 = Process  ENTER = Refresh
```

Figure 10. Installation Planning Panel

- a. See the installation worksheet (Table 8 on page 64) and enter:
 - An "M" in the **Install To** column for each product you selected to be installed onto minidisks.
 - An "F" in the **Install To** column for each product you selected to be installed into the VMSYS file pool.
- b. Place a nonblank character next to the System Default Language you selected for your system (see the installation worksheet, Table 8 on page 64).
- c. Place a nonblank character in front of the DASD model that matches the *DASD type and model* recorded on the installation worksheet (Table 8 on page 64). If you are installing to FBA (SCSI), the size of the FBA disk must be at least 3.5 GB.
- d. Press F5 to process your selections.

Note: The output you see may be different due to your planning choices.

F5

```
HCPIPX8475I THE PRODUCTS YOU SELECTED TO LOAD TO MINIDISK ARE:  
VM RSCS TCPIP OSA ICKDSF  
DIRM RACF PERFTK VMHCD
```

```
THE PRODUCTS YOU SELECTED TO LOAD TO SFS ARE:  
NONE
```

```
THE SYSTEM DEFAULT LANGUAGE SELECTED:  
AMENG
```

```
THE DASD TYPE YOU SELECTED TO LOAD ON IS:  
type
```

```
THE DASD NEEDED TO LOAD z/VM ARE:  
610RES 610SPL 610PAG...
```

```
HCPINP8392I INSTPLAN EXEC ENDED SUCCESSFULLY  
Ready; T=n.nn/n.nn hh:mm:ss
```

2. Make sure the number of DASD selected on the installation worksheet (Table 8 on page 64) matches the number of DASD listed in the HCPIPX8475I message.

Step 2. Verify the Volumes Needed for Installation are Available

In this step, you will:

- Attach the volumes needed for installation.

1. If you are installing to 3390 skip to substep 9 on page 111.
2. If the SCSI disks you are installing to are defined as minidisks on your installation user ID, skip to substep 8 on page 111.
3. If the SCSI disks you are installing to have already been defined using the SET EDEVICE command and are already online, skip to substep 8 on page 111. If they are defined but offline skip to substep 7 on page 111. If not yet defined continue with the next substep.
4. See the installation worksheet (Table 8 on page 64) and query each DASD address to verify it is not already defined for a different device (see example below). If the address is already in use, choose a different *dasdaddr* and verify that address does not exist.

For each DASD address:

```
query dasdaddr
HCPQVD040E Device dasdaddr does not exist
Ready(00040);
```

Record each verified DASD address in the *DASD Address* column on the installation worksheet (Table 8 on page 64) and in the *edev* column on the SCSI Device Definition Worksheet (Table 9 on page 64).

5. To define the SCSI disks, you need to know which FCP addresses are valid for your SCSI disks. If you know the FCP addresses associated with your SCSI disk addresses skip this substep. If only the channel path id is known, issue the Query CHPID command to display all FCP addresses associated with the path. For example, if the channel path is X'66', issue:

```
query chpid 66
Path 66 online to devices 517C 5319 550D 8100 8101 8102 8103 8104
Path 66 online to devices 8105 8106 8107 8108 8109 810A 810B 810C
Path 66 online to devices 810D 810E 810F 8110 8111 8112 8113 8114
Path 66 online to devices 8115 8116 8117 8118 8119 811A 811B 811C
Path 66 online to devices 811D 811E 811F
```

6. To define the SCSI disks, use the information recorded in the installation worksheet (Table 8 on page 64) and SCSI Device Definition Worksheet (Table 9 on page 64).

For each DASD:

- a. Select and record a free FCP address for each *edev*. You should use one FCP device for the 610RES and a different (or multiple different) FCPs for the other disks.

```
query fcp free
```

Choose a device from the output. Record a FCP address for each *edev* in the FCP Address column of the SCSI Device Definition Worksheet (Table 9 on page 64).

- b. Define the device address.

```
set edevice dasdaddr type fba attr scsi fcp_dev fcpn wwpn www lun lll
```


Verify the Volumes Needed for Installation are Available

dasdaddr

The edevice address from Table 9 on page 64.

fcpn

FCP address (you should use one FCP device for the 610RES and a different, or multiple different, FCPs for the other disks).

www

World Wide port number.

/// LUN address.

7. Vary on the SCSI disks. Repeat for each disk.

vary on *dasdaddr*

8. Note the following changes needed in the SYSTEM CONFIG file for future IPLs.

- When performing a second-level installation to SCSI disk, the EDEV statements are added to the SYSTEM CONFIG as comments. If you want to IPL the system first-level, remove the *'/*...*/* pairs from the EDEV statements in the SYSTEM CONFIG file.
- If the SCSI disks you are installing to are defined as minidisks on your installation user ID, they cannot be IPLed first-level; therefore the SYSTEM CONFIG file is not updated to include any EDEV statements.

For information on updating the SYSTEM CONFIG file, see *z/VM: CP Planning and Administration*.

9. Attach all the DASD listed in the installation worksheet (Table 8 on page 64) that are not already attached. Enter the following ATTACH command for each DASD.

```
attach dasdaddr *  
DASD dasdaddr ATTACHED TO userID dasdaddr  
:  
Ready; T=n.nn/n.nn hh:mm:ss
```

dasdaddr

Address of the DASD.

Step 3. Run INSTDVD

In this step, you will:

- Run INSTDVD.

1. Access the minidisk with the new install code.

```
access 22CC c
Ready;
```

2. If installing from a VM minidisk, access the minidisk that contains the image files as W.

```
access diskaddr w
Ready; T=n.nn/n.nn hh:mm:ss
```

dasdaddr
Address of the minidisk where the image files were copied.

3. Run INSTDVD to restore the image files to DASD.

```
instdvd
**** NOW EXECUTING INSTDVD EXEC ON date AT time ****
```




Figure 11. z/VM DVD Install Format and Restore Panel (3390 Model Layout)

- a. If you want to change the labels of the SPOOL, PAGE, or USER packs, fill in the DASD LABEL field with the new labels. You cannot change the 610RES label. If you are installing second-level and you wish to change installation pack labels, the installation user ID must be able to issue the DEFINE MDISK command. The IBM default privilege class for this command is class A. The DEFINE MDISK command also requires the user ID to have DEVMAINT on the OPTION directory statement in its directory entry.
- b. Fill in the DASD addresses using the information from the installation worksheet (Table 8 on page 64). For more information and help, press F1.
- c. Place a nonblank character in the DO NOT FORMAT DASD column only if you have already CP formatted your DASD for this installation using ICKDSF or CPFMTXA. The DASD will be labeled, but not formatted.

d. Press F5 to process.

F5

HCPDCX8377R YOU HAVE SELECTED TO FORMAT THE FOLLOWING DASD:

HCPDCX8483R YOU HAVE SELECTED NOT TO FORMAT YOUR DASD.
THIS ASSUMES YOU HAVE ALREADY FORMATTED THE
DASD AND THIS EXEC WILL ONLY RELABEL AS
FOLLOWS

Depending on whether you chose to format your
DASD, you will receive either message
HCPDCX8377R or HCPDCX8483R.

610RES *dasdaddr*
lblspl dasdaddr
lblpag dasdaddr
lblw01 dasdaddr

DO YOU WANT TO CONTINUE ? (Y|N)

y

HCPDCX8490I NOW {FORMATTING|LABELING} DASD *dasdaddr*
HCPDCX8490I NOW {FORMATTING|LABELING} DASD *dasdaddr*

⋮
HCPDCX8380I RESTORING IIS TO 610RES and *lblspl*
{FBIIIS* | CKDIIS*}

This message is not displayed if installing from VM
minidisk.

DMSRXS1408W File TCPIP DATA * not found

You might not receive this message.

{ECKDREST|MDREST}: WROTE *nnnn* {TRACKS|BLOCKS} ON *addr*, RC=0
HCPDCX8341I LOAD OF THE SYSTEM IIS COMPLETED SUCCESSFULLY

{FBASPL* | CKDSPL*}

This message is not displayed if installing from VM
minidisk.

DMSRXS1408W File TCPIP DATA * not found

You might not receive this message.

PROCESSING {fbasp100|ckdsp100}

Processing messages are not displayed if installing
from VM minidisk.

⋮
PROCESSING {fbasp1nn|ckdsp1nn}
{MDREST|ECKDREST}: WROTE *nnnn* {BLOCKS|TRACKS} ON *addr*, RC=0
HCPDCX8341I LOAD OF THE SYSTEM SPOOL SPACE COMPLETED SUCCESSFULLY

HCPDCX8490I NOW ALLOCATING DASD *addr* (RES PACK)

HCPDCX8490I NOW ALLOCATING DASD *addr* (SPOOLING)

HCPDCX8490I NOW ALLOCATING DASD *addr* (PAGING)

The minidisks with the END option specified in this directory will not be included
in the following DISKMAP file.

File USER DISKMAP A has been created.

HCPIND8392I INSTDIR EXEC ENDED SUCCESSFULLY

HCPIDV8341I CREATION OF USER DIRECTORY COMPLETED SUCCESSFULLY

Messages received for each minidisk loaded (DVD drive and FTP server directory)

```
HCPILB8440I NOW LOADING {FBACuu | CKDcuu}, DISK xxx OF yyy
{FBACuu* | CKDcuu*}
DMSRXS1408W File TCPIP DATA * not found
PROCESSING {FBACuu00|CKDcuu00}
:
PROCESSING {FBACuunn|CKDcuunn}
{MDREST|ECKDREST}: WROTE nnnn {BLOCKS|TRACKS} ON addr, RC=0
```

If the installation fails while processing the disks loaded during DVD or FTP server directory installation, issue INSTDVD to try again. INSTDVD will resume where processing failed.

Messages received for each minidisk loaded (VM minidisk)

```
HCPILB8440I NOW LOADING {FBACuu | CKDcuu}, DISK xxx OF yyy
DMSRXS1408W File TCPIP DATA * not found
```

```
{MDREST|ECKDREST}: WROTE nnnn {BLOCKS|TRACKS} ON addr, RC=0
```

If the installation fails while processing the disks loaded during VM minidisk installation, and message HCP8342E was not received, then issue INSTDVD again. INSTDVD will resume where processing failed.

If message HCP8342E was received, indicating the PIPE DVDDECOD *xxxnnn* command failed with return code 3, then perform the following:

- 1) Verify the image files for the disk (*xxxnnn*) indicated in the message have a fixed (F) file format and a logical record length (LRECL) of 1028.

If an image file has an incorrect file format or logical record length, the file was copied incorrectly. In this situation, you must erase the image files off the minidisk, copy the image files again using the correct parameters, access the minidisk as W, and issue INSTDVD again. To copy the image files again, see From a VM Minidisk, "Step 1. Set up the User ID for Installation" on page 100, and repeat substeps 6 through 9.

- 2) Verify all image files needed for the disk exist and the number of records for each are correct.
 - If the disk (*xxxnnn*) indicated in the message is the 500 disk, the correct number of records can be found in the file 610rsu.dvdimage on the RSU DVD.
 - For all other disks, the correct number of records can be found in the file 610prod.dvdimage on the z/VM system DVD.

If an image file contains an incorrect number of records, the file was copied incorrectly. In this situation, you must erase any files with an incorrect number of records off the minidisk, copy the files using the correct parameters, access the minidisk as W, and issue INSTDVD again. To copy the image files again, see From a VM Minidisk, "Step 1. Set up the User ID for Installation" on page 100, and repeat substeps 6 through 9.

Messages received if installing from a DVD drive

HCPIRU8484R PLEASE PLACE THE SYSTEM RSU DVD
IN THE DRIVE, THEN TYPE GO TO
CONTINUE OR TYPE EXIT TO QUIT.

Place the RSU DVD in the DVD drive and wait until the light on the DVD drive goes out or stops blinking, then enter **go**.

go

If you enter **exit**, your installation will **not** complete successfully. You must run the INSTDVD command and enter **go** to load the RSU files before you can continue with the installation.

If the installation fails while loading the RSU DVD, issue INSTDVD to try again.

```
{FBA500* | CKD500*}
DMSRXS1408W File TCPIP DATA * not found
{MDREST|ECKDREST}: WROTE nnnn {BLOCKS|TRACKS} ON addr, RC=0
```

```
z/VM USER DIRECTORY CREATION PROGRAM - VERSION 6 RELEASE 1.0
EOJ DIRECTORY UPDATED
HCPDIR494I User directory occupies nn disk pages
HCPIDV8341I USER DIRECTORY HAS BEEN BROUGHT ONLINE SUCCESSFULLY
HCPDIAL6798I VOLUME ID IS 610RES
HCPDIAL6797I MINIDISK VOLID AT OFFSET nnnn IS MNTCF1
HCPIDV8341I SALIPL COMMAND HAS COMPLETED SUCCESSFULLY
{MDDUMP|ECKDDUMP}: {READ} nnnn {BLOCKS|TRACKS} FROM 2CF1, RC=0
{MDREST|ECKDREST}: WROTE nnnn {BLOCKS|TRACKS} ON addr, RC=0
HCPIDV8341I {MDDUMP|ECKDDUMP} OF 2CF1 COMPLETED SUCCESSFULLY
HCPIDV8338I NOW EXECUTING COPY OF 22CC TO 2CC STEP
{MDDUMP|ECKDDUMP}: {READ} nnnn {BLOCKS|TRACKS} FROM 22CC, RC=0
{MDREST|ECKDREST}: WROTE nnnn {BLOCKS|TRACKS} ON addr, RC=0
HCPIDV8341I {MDDUMP|ECKDDUMP} OF 22CC COMPLETED SUCCESSFULLY
HCPIDV8392I INSTDVD EXEC ENDED SUCCESSFULLY
Ready; T=n.nn/n.nn hh:mm:ss
```

Step 4. IPL the new z/VM System

In this step, you will:

- IPL the new z/VM system.

Note: Contention for service by the devices on shared control units may result in this substep taking longer than it would when you are installing a first-level system.

1. Reset your virtual machine and make sure the z/VM system will recognize your terminal as a 3277, 3278, or 3279.

```
system clear
Storage cleared - system reset.
```

```
terminal conmode 3270
```

Attention: Issue the QUERY DASD ATTACH * command to make sure that any DASD with the same labels that you are using for installation are not already attached. You must detach any other DASD with these labels now to prevent bringing them online.

2. Verify you have 64 MB of virtual storage. If you have less than 64 MB of virtual storage, issue the DEFINE command to set your virtual storage to 64 MB.

```
query virtual storage
STORAGE = nnnnM
```

```
define storage 64M
STORAGE = 64M
Storage cleared - system reset
```

3. Set the virtual machine mode to ESA.

```
set machine esa
```

4. Query the console to determine the virtual console address (*consaddr*). This address is required in the next substep.

```
query console
CONS consaddr ON LDEV nnnn TERM START
consaddr CL T NOCONT NOHOLD COPY 001 READY FORM STDN
consaddr TO userID dev DIST nnnn FLASHC 000 DEST OFF
consaddr FLASH CHAR MDFY 0 FCB LPP OFF
consaddr 3270 NOEOF OPEN nnnn NOKEEP NOMSG NONAME
consaddr SUBCHANNEL = nnnn
```

5. IPL the new z/VM system you loaded to the system residence device (610RES).

```
ipl dasdaddr clear loadparm consaddr
```

CLEAR is necessary. Do not omit it.

```
dasdaddr
Address of the system residence device
(610RES).
```

```
consaddr
Virtual console address determined in substep 4.
```

The Stand Alone Program Loader panel displays after issuing the IPL command.

```

STAND ALONE PROGRAM LOADER: z/VM VERSION 6 RELEASE 1.0

DEVICE NUMBER:  dasdaddr  MINIDISK OFFSET:  nnnnnnnn  EXTENT:  1
MODULE NAME:     CLOAD    LOAD ORIGIN:      2000

-----IPL PARAMETERS-----
cons=consaddr

-----COMMENTS-----

-----

9= FILELIST  10= LOAD  11= TOGGLE EXTENT/OFFSET

```

Figure 12. Sample Stand Alone Program Loader Panel

6. Move the cursor to the IPL PARAMETERS field and type

cons=consaddr

dasdaddr

Address of the system residence device
(610RES).

consaddr

Virtual console address determined in substep 4
on page 116. Spaces are not allowed around the
equal sign.

7. Press F10 to load.

F10

```

hh:mm:ss z/VM V6 R1.0
          SERVICE LEVEL nnnn (64-BIT)

hh:mm:ss SYSTEM NUCLEUS CREATED ON yyyy-mm-dd AT hh:mm:ss,
          LOADED FROM 610RES

hh:mm:ss *****
hh:mm:ss * LICENSED MATERIALS - PROPERTY OF IBM* *
hh:mm:ss * 5741-A07 (C) COPYRIGHT IBM CORP. 1983, *
hh:mm:ss * 2009. ALL RIGHTS RESERVED. *
hh:mm:ss * US GOVERNMENT USERS RESTRICTED RIGHTS - *
hh:mm:ss * USE, DUPLICATION OR DISCLOSURE *
hh:mm:ss * RESTRICTED BY GSA ADP SCHEDULE CONTRACT *
hh:mm:ss * WITH IBM CORP. *
hh:mm:ss * *
hh:mm:ss * * TRADEMARK OF INTERNATIONAL BUSINESS *
hh:mm:ss * * MACHINES *
hh:mm:ss *****
hh:mm:ss HCPZC06718I Using parm disk 1 on volume 610RES (device xxxx).
hh:mm:ss HCPZC06718I Parm disk resides on blocks/cylinders xxx through xxx.

```

IPL the new z/VM system

⋮

You might receive an informational message, HCPIISU951I, about volumes not mounted. If you are not using those volume labels, ignore this message.

Note: If you receive informational message HCPIIS954I for your 610RES volume (for example, DASD 5016 VOLID 610RES IS A DUPLICATE OF DASD 5516), you can ignore this message and proceed. For any other occurrence of HCPIIS954I, you have duplicate volumes with the same label. Make note of the duplicate volumes and enter SHUTDOWN at the next prompt. Detach the duplicate volumes and then go back to substep 1 on page 116.

```
hh:mm:ss Start ((Warm|Force|COLD|CLEAN) (DRain)
              (Disable) (NODIRect) (NOAUTOlog)) or (SHUTDOWN)
```

cold drain noauto log

Because there is no data or accounting information to recover, use COLD DRAIN to request a cold start. Use NOAUTOLOG at this point because you cannot have the servers and all user IDs logged on.

```
NOW hh:mm:ss {EST|EDT} weekday yyyy-mm-dd
Change TOD clock (yes|no)
```

no

CP logs on the primary system operator user ID (OPERATOR).

```
hh:mm:ss The directory on volume 610RES at address nnnn
         has been brought online.
```

```
hh:mm:ss HCPWRS2513I
```

```
hh:mm:ss HCPWRS2513I Spool files available nnnn
```

Note: Depending on the type of spool files available, you might receive the following prompt:

Spool Files Prompt

```
hh:mm:ss HCPWRS2513I
hh:mm:ss HCPWRS2513I Spool files on offline volumes {nnnn|NONE}
hh:mm:ss HCPWRS2513I Spool files with I/O errors {nnnn|NONE}
hh:mm:ss HCPWRS2513I Spool files with control errors {nnnn|NONE}
hh:mm:ss HCPWRS2513I Spool files to be discarded {nnnn|NONE}
hh:mm:ss HCPWRS2513I -----
hh:mm:ss HCPWRS2513I Total files to be deleted nnnn
hh:mm:ss HCPWRS2511A
hh:mm:ss HCPWRS2511A Spool files will be deleted because of
                   COLD start.
hh:mm:ss HCPWRS2511A No files have been deleted yet.

hh:mm:ss HCPWRS2511A To continue COLD start and delete files,
                   enter GO.
hh:mm:ss HCPWRS2511A To stop COLD start without deleting
                   files, enter STOP.
```

go

The system gives you an opportunity to stop the cold start and save your spool files. You do not need to save any spool files at this time; answer GO.


```

hh:mm:ss HCPWRS2512I Spooling initialization is complete.
hh:mm:ss DASD nnnn dump unit CP IPL pages nnnn
hh:mm:ss HCPAAU2700I System gateway ZVMV6R10 identified.
hh:mm:ss z/VM Version 6 Release 1.0, Service Level 0000 (64-bit),
built on IBM Virtualization Technology
hh:mm:ss There is no logmsg data
hh:mm:ss FILES: NO RDR, NO PRT, NO PUN
hh:mm:ss LOGON AT hh:mm:ss timezone day mm/dd/yy
hh:mm:ss GRAF nnnn LOGON AS OPERATOR USERS = n
hh:mm:ss HCPIOP952I nnnnM system storage
hh:mm:ss FILES: nnnnnnnn RDR, nnnnnnnn PRT, NO PUN
hh:mm:ss HPCRCR8082I Accounting records are accumulating for userid DISKACNT.

```

8. Disconnect from the OPERATOR user ID.

```

disconnect
DISCONNECT AT hh:mm:ss {EST|EDT} weekday mm/dd/yy

```

Press enter or clear key to continue

ENTER

9. Log on as MAINT.

ENTER

The default password for MAINT is MAINT.

```

logon maint
HCPLNM102E 080D DASD force R/O; R/W by operator
HCPLNM101E 080E DASD force R/O; R/O by operator
z/VM Version 6 Release 1.0, Service Level 0000 (64-bit),
built on IBM Virtualization Technology
There is no logmsg data
FILES: nnnn RDR, NO PRT, NO PUN
LOGON AT hh:mm:ss timezone day mm/dd/yy
z/VM V6.1.0 yyyy-mm-dd hh:mm

```

ENTER

Ready; T=n.nn/n.nn hh:mm:ss

Step 5. Run INSTVM

In this step, you will:

- Run INSTVM with the DVD option to complete installation tasks.

Note: Running the INSTVM requires a full screen terminal with at least 20 lines.

1. IPL CMS to verify the CMS saved system is available.

```
ipl cms
z/VM V6.1.0   yyyy-mm-dd hh:mm
```

ENTER

```
Ready; T=n.nn/n.nn hh:mm:ss
```

Note: If the CMS saved system does not exist, there is a problem with spool space. You must resolve the problem before continuing.

2. Run INSTVM to complete the installation of z/VM from DVD.

```
instvm dvd
**** NOW EXECUTING INSTVM EXEC ON date AT time ****
HCPPLD8338I NOW EXECUTING ALLOCATION OF SYSTEM RESIDENCE PACK
HCPPLD8338I NOW EXECUTING UPDATE OF $MOVE$ $FILE$ C
HCPPLD8341I POSTLOAD FUNCTION "INSTALLATION CLEANUP" COMPLETED SUCCESSFULLY
HCPPLD8338I NOW EXECUTING DIRECTORY CLEANUP
HCPPLD8341I POSTLOAD FUNCTION "DIRECTORY CLEANUP AND ADD HELP DISK LINKS" COMPLETED SUCCESSFULLY
HCPPLD8338I NOW EXECUTING THE DIRECTXA COMMAND TO BRING THE UPDATED USER DIRECTORY ONLINE
HCPPLD8341I POSTLOAD FUNCTION "BRING UPDATED DIRECTORY ONLINE" COMPLETED SUCCESSFULLY

HCPPLD8392I POSTLOAD EXEC ENDED SUCCESSFULLY
DMSACC724I 2CC replaces C (2CC)
HCPIDV8493I ISSUING XAUTOLOG FOR VMSERVU
AUTO LOGON ***          VMSERVU  USERS = n
HCPCLS6056I XAUTOLOG information for VMSERVU: The IPL command is verified by the IPL
command processor.
VMSERVU : z/VM V6.1.0   yyyy-mm-dd hh:mm
VMSERVU : DMSACP723I B (193) R/O
VMSERVU : DMSWV1117I FILESERV processing begun at hh:mm:ss on dd month yyyy
VMSERVU : DMSWV1121I VMSERVU DMSPARMS A1 will be used for FILESERV processing
VMSERVU : DMSWV1121I VMSYSU POOLDEF A1 will be used for FILESERV processing
VMSERVU : DMS5BB3045I Ready for operator communications
HCPIDV8493I ISSUING XAUTOLOG FOR VMSERVR
AUTO LOGON ***          VMSERVR  USERS = n
HCPCLS6056I XAUTOLOG information for VMSERVR: The IPL command is verified by the IPL
command processor.
VMSERVR : z/VM V6.1.0   yyyy-mm-dd hh:mm
VMSERVR : DMSACP723I B (193) R/O
VMSERVR : DMSWV1117I FILESERV processing begun at hh:mm:ss on dd month yyyy
VMSERVR : DMSWV1121I VMSERVR DMSPARMS A1 will be used for FILESERV processing
VMSERVR : DMSWV1121I VMSYSR POOLDEF A1 will be used for FILESERV processing
VMSERVR : DMS6LG3335I CRR log recovery begins at mm-dd-yy hh:mm:ss
VMSERVR : DMS6LG3335I CRR log recovery completes at mm-dd-yy hh:mm:ss
VMSERVR : DMS5BB3045I Ready for operator communications
```

Extra messages received if all products were loaded to minidisks

```

DASD 0804 DETACHED
HCPIDV8493I ISSUING XAUTOLOG FOR VMSERVS
AUTO LOGON ***          VMSERVS USERS = n
HCPCLS6056I XAUTOLOG information for VMSERVS: The IPL command is verified by the IPL
command processor.
VMSERVS : z/VM V6.1.0    yyyy-mm-dd hh:mm
VMSERVS : DMSACP723I B (193) R/O
VMSERVS : DMSWV1117I FILESERV processing begun at hh:mm:ss on dd month yyyy
VMSERVS : DMSWV1121I VMSERVS DMSPARMS A1 will be used for FILESERV processing
VMSERVS : DMS4PD3400I Initializing begins for DDNAME = CONTROL
VMSERVS : DMS4PD3400I Initializing ends for DDNAME = CONTROL
VMSERVS : DMS4PD3400I Initializing begins for DDNAME = MDK00001
VMSERVS : DMS4PD3400I Initializing ends for DDNAME = MDK00001
VMSERVS : DMS4PD3400I Initializing begins for DDNAME = MDK00002
VMSERVS : DMS4PD3400I Initializing ends for DDNAME = MDK00002
VMSERVS : DMS4PD3400I Initializing begins for DDNAME = LOG1
VMSERVS : DMS4PD3400I Initializing ends for DDNAME = LOG1
VMSERVS : DMS4PD3400I Initializing begins for DDNAME = LOG2
VMSERVS : DMS4PD3400I Initializing ends for DDNAME = LOG2
VMSERVS : DMS5FD3032I File pool server has terminated
VMSERVS : DMSWV1120I File VMSYS POOLDEF A1 created or replaced
VMSERVS : DMSWV1117I FILESERV processing ended at hh:mm:ss on dd month yyyy
RDR FILE nnnn SENT FROM VMSERVS PUN WAS nnnn RECS nnnn CPY 001 A NOHOLD NOKEEP
VMSERVS : File FILESERV VALID A3 sent to MAINT at ZVMV6R10 on mm/dd/yy hh:mm:ss
VMSERVS : Ready; T=n.nn/n.nn hh:mm:ss

HCPQCS150A User VMSERVS has issued a VM read
VMSERVS : CONNECT= nn:nn:nn VIRTCPU= nnn:nn.nn TOTCPU= nnn:nn.nn
VMSERVS : LOGOFF AT hh:mm:ss timezone day mm/dd/yy BY MAINT
USER DSC LOGOFF AS VMSERVS USERS = 2    FORCED BY MAINT
DASD 0804 DETACHED

```

```

HCPIDV8493I ISSUING XAUTOLOG FOR VMSERVS
AUTO LOGON ***          VMSERVS USERS = n
HCPCLS6056I XAUTOLOG information for VMSERVS: The IPL command is verified by the IPL
command processor.
VMSERVS : z/VM V6.1.0    yyyy-mm-dd hh:mm
VMSERVS : DMSACP723I B (193) R/O
VMSERVS : DMSWV1117I FILESERV processing begun at hh:mm:ss on dd month yyyy
VMSERVS : DMSWV1121I VMSERVS DMSPARMS A1 will be used for FILESERV processing
VMSERVS : DMSWV1121I VMSYS POOLDEF A1 will be used for FILESERV processing
VMSERVS : DMS5BB3045I Ready for operator communications

```

You might not receive one or more of the following messages

```

HCPIDV8338I UPDATING SYSTEM TABLES AND CLEANING UP FILEPOOL DIRECTORIES
RC=0 from EXEC OPENVM UNMOUNT /
RC=0 from EXEC OPENVM UNMOUNT /
RC=0 from EXEC OPENVM UNMOUNT /
RC=0 from EXEC OPENVM UNMOUNT /
RC=0 from EXEC OPENVM UNMOUNT /

```

```

HCPIFP8392I INSTPOOL EXEC ENDED SUCCESSFULLY
HCPIVM8392I INSTVM EXEC ENDED SUCCESSFULLY
Ready; T=n.nn/n.nn hh:mm:ss

```

Run INSTVM

After this point, when you IPL the system, you should use the default IPL parameters and should no longer use COLD DRAIN NOAUTOLOG.

Step 6. Run SERVICE

In this step, you will:

- Load the service files from the recommended service upgrade (RSU) servlink.

1. Log on as MAINT.

```

ENTER
logon maint
:
Ready; T=n.nn/n.nn hh:mm:ss

```

The default password for MAINT is MAINT.

2. Make sure the file pool is available.

If you receive message DMS1153E, indicating the MAINT file pool is unavailable or unknown, you need to XAUTOLOG VMSESRVS, VMSERVU, and VMSERVR.

```

query limits all
Userid  Storage Group  4K Block Limit  4K Blocks Committed  Threshold
userid1      2              n              n-nn%             nn%
userid2      2              n              n-nn%             nn%
:
Ready; T=n.nn/n.nn hh:mm:ss

```

3. IPL CMS.

```

ipl cms
z/VM V6.1.0   yyyy-mm-dd hh:mm

```

```

ENTER
Ready; T=n.nn/n.nn hh:mm:ss

```

4. Access the disk containing the RSU servlink as C.

```

access diskaddr c
DMSACC724I diskaddr replaces C (2CC)
Ready;

```

diskaddr
Address containing the RSU servlink. If you received and loaded a RSU or COR from IBM Support to a minidisk on your first-level user ID, specify that address. Otherwise, use address 500.

5. List the file names of the RSU envelopes on the minidisk accessed as C.

```

listfile * servlink c
610xRSUn servlink c
610xRSUn servlink c

```

x RSU number.
n Volume number.

6. Run SERVICE.

Run SERVICE

```

service all envfn1 envfn2 ...
VMFSRV2760I SERVICE processing started
:
VMFSRV2760I SERVICE processing completed
successfully
Ready; T=n.nn/n.nn hh:mm:ss

```

envfn1
File name for the first envelope 610xRSU1.

envfn2 ...
File name for the second envelope 610xRSU2,
and so on.

7. View the SERVICE messages log (VMFVIEW SERVICE) and handle any nonzero return code, if necessary. Base your action on the following table.

If you received . . .	Then . . .
Return code 4	<ol style="list-style-type: none"> 1. Issue VMFVIEW SERVICE. 2. Ignore any warning messages listed in the note below. Take appropriate actions based on other warning messages you receive. 3. Go to "Step 7. Run PUT2PROD" on page 125.
A return code greater than 4	<ol style="list-style-type: none"> 1. Issue VMFVIEW SERVICE and check for warning and error messages. 2. Ignore any warning messages listed in the note below. Take appropriate actions based on other warning messages you receive. 3. Correct all errors reported in the error messages. 4. Restart by issuing the SERVICE command as displayed in the message VMFSRV2310W. 5. If you receive a nonzero return code, repeat substep 7. 6. Go to "Step 7. Run PUT2PROD" on page 125.

Note: You can ignore the following messages and their associated VMF1966W message.

- DMSLI0201W The following names are undefined: ISPLINK ARIPRDI
- DMSLI0201W The following names are undefined: DMSDSCSC
- DMSLI0201W The following names are undefined: DMSUSRX1 DMSUSRX2
- DMSLI0202W Duplicate identifier (Associated with object IOACMAIN MODULE.)
- DMSLKD004W Warning messages issued (Associated with objects ILBONBL, ILBONTR, ILBOREC, ILBORNT, ILBOSND, ILBOSNT, and ILBOSSN.)
- VMFSRV1221W The Stand Alone Dump Utility must be rebuilt.

8. Use the VMFUPDAT SYSMEMO command to review any memos that were received with this service.

Step 7. Run PUT2PROD

In this step, you will:

- Run PUT2PROD to place the product into production.

1. Log on as MAINT.

```

ENTER
logon maint
:
Ready; T=n.nn/n.nn hh:mm:ss

```

The default password for MAINT is MAINT.

2. Make sure the file pool is available.

If you receive message DMS1153E, indicating the MAINT file pool is unavailable or unknown, you need to XAUTOLOG VMSEVS, VMSERVU, and VMSERVR.

```

query limits all
Userid  Storage Group 4K Block Limit 4K Blocks Committed Threshold
userid1      2          n          n-nn%      nn%
userid2      2          n          n-nn%      nn%
:
Ready; T=n.nn/n.nn hh:mm:ss

```

3. IPL CMS and access the VMSES/E test build disk.

```

ipl cms
z/VM V6.1.0   yyyy-mm-dd hh:mm

```

```

ENTER
Ready; T=n.nn/n.nn hh:mm:ss

```

```

access 5E6 B
Ready; T=n.nn/n.nn hh:mm:ss

```

4. Run PUT2PROD.

```

put2prod
VMFP2P2760I PUT2PROD processing started
:
VMFP2P2760I PUT2PROD processing completed successfully
Ready; T=n.nn/n.nn hh:mm:ss

```

5. Handle a nonzero return code. Base your action on the following table.

If you received . . .	Then . . .
Return code 4	<ol style="list-style-type: none"> Issue VMFVIEW PUT2PROD. Ignore any warning messages listed in the note below. Take appropriate actions based on other warning messages you receive.

Run PUT2PROD

If you received . . .	Then . . .
A return code greater than 4	<ol style="list-style-type: none"><li data-bbox="568 210 1421 241">1. Issue VMFVIEW PUT2PROD and check for warning and error messages.<li data-bbox="568 241 1421 304">2. Ignore any warning messages listed in the note below in this table. Take appropriate actions based on other warning messages you receive.<li data-bbox="568 304 1421 336">3. Correct all errors reported in the error messages.<li data-bbox="568 336 1421 367">4. Issue IPL CMS.<li data-bbox="568 367 1421 399">5. Issue PUT2PROD.<li data-bbox="568 399 1421 468">6. If you receive a nonzero return code, repeat substep 5 on page 125.

Note: You can ignore the following messages.

- DMSDCS1083E Saved segment \$\$DMY\$\$ does not exist
- DMSWLG292W Text data will be loaded at '20000'x in user area; user data may be overwritten.
- DTCPRD3043W File *fn ft fm* has been updated; It's contents should be reviewed for changes that may affect your use of this file.
- TCPMSM0002W File TCPIP DATA cannot be located
- TCPMSM0002W TCP/IP appears not to have been configured

Step 8. Shut Down and Re-IPL the System

In this step, you will:

- Shut down the V6.1 system.
- IPL the V6.1 system using the new CP nucleus.

1. Shut down and re-IPL the V6.1 system.

shutdown reipl

SYSTEM SHUTDOWN STARTED
Ready; T=*n.nn/n.nn hh:mm:ss*

The shut down message is displayed on all enabled consoles.

HCPWRP963I STARTING SHUTDOWN STEP . . .
:
HCPWRP962I VM SHUTDOWN COMPLETED IN *n* SEC
HCPWRP9277I SYSTEM TERMINATION COMPLETE,
ATTEMPTING RESTART

HCP963I, HCP962I, and HCP9277I will appear on the operator's console.

hh:mm:ss HCPWRP9277I SYSTEM TERMINATION COMPLETE.
ATTEMPTING RESTART

hh:mm:ss z/VM SYSTEM RESTART FROM SHUTDOWN REIPL

hh:mm:ss z/VM V6 R1.0
SERVICE LEVEL *nnnn* (64-BIT)

hh:mm:ss SYSTEM NUCLEUS CREATED ON *yyyy-mm-dd* AT *hh:mm:ss*,
LOADED FROM 610RES

hh:mm:ss *****

hh:mm:ss * LICENSED MATERIALS - PROPERTY OF IBM* *

hh:mm:ss * 5741-A07 (C) COPYRIGHT IBM CORP. 1983, *

hh:mm:ss * 2009. ALL RIGHTS RESERVED. *

hh:mm:ss * US GOVERNMENT USERS RESTRICTED RIGHTS - *

hh:mm:ss * USE, DUPLICATION OR DISCLOSURE *

hh:mm:ss * RESTRICTED BY GSA ADP SCHEDULE CONTRACT *

hh:mm:ss * WITH IBM CORP. *

hh:mm:ss *

hh:mm:ss * * TRADEMARK OF INTERNATIONAL BUSINESS *

hh:mm:ss * MACHINES *

hh:mm:ss *****

hh:mm:ss HCPZC06718I Using parm disk 1 on volume *valid* (device *xxxx*).

hh:mm:ss HCPZC06718I Parm disk resides on cylinders *xx* through *xx*.

:

Note: If you receive informational message HCPIIS954I for your 610RES volume (for example, DASD 505A VOLID 610RES IS A DUPLICATE OF DASD 5516), you can ignore this message and proceed. For any other occurrence of HCPIIS954I, you have duplicate DASD with the same label and must correct this error before continuing.

hh:mm:ss The directory on volume 610RES at address *nnnn*
has been brought online.

hh:mm:ss HCPWRS2513I

hh:mm:ss HCPWRS2513I Spool files available {*nnnn*|none}

hh:mm:ss HCPWRS2512I Spooling initialization is complete.

:

hh:mm:ss FILES: *nnn* RDR, *nnn* PRT, *nnn* PUN

hh:mm:ss LOGON AT *hh:mm:ss* {EST|EDT} *weekday mm/dd/yy*

:

hh:mm:ss HCPIOP952I *nnnnM* system storage

hh:mm:ss FILES: *nnnnnnn* RDR, *nnnnnnn* PRT, NO PUN

Shut Down and Re-IPL the System

Message HCP952I tells you the amount of storage available.

The files message refers to operator spool files.

CP automatically disconnects from the primary system operator user ID (OPERATOR).

```
hh:mm:ss HCPUS0967I Disconnect OPERATOR - system
          restarted SHUTDOWN and system console
          not VM operator console
hh:mm:ss HCPCRC8082I Accounting records are accumulating for userid DISKACNT
hh:mm:ss DISCONNECT AT hh:mm:ss {EST|EDT} weekday mm/dd/yy
hh:mm:ss Press enter or clear key to continue
```

ENTER

Press Enter or the Clear key to continue.

2. Log on as MAINT.

ENTER

The password for MAINT is MAINT.

```
logon maint
:
Ready; T=n.nn/n.nn hh:mm:ss
```

What to do next

See Part 3, "Post z/VM System Installation," on page 129.

Part 3. Post z/VM System Installation

Part 3 contains the following:

- Procedures for configuring a basic TCP/IP network connection.
- Procedures for backing up the z/VM system.
- Procedures for creating IPLable utility tapes.
- Procedures for migrating customized files and service for products that are preinstalled on the z/VM installation media.
- Information about the licensed products and features that are preinstalled on the z/VM installation media.

Post z/VM System Installation

Chapter 8. Configure and Back Up the System

In this chapter, you will:

- Configure a basic TCP/IP network connection (optional).
- Back up the z/VM system to tape or DASD.
- Create IPLable utility tapes.

Step 1. Configure TCP/IP for an Initial Network Connection

In this step, you will:

- Configure a basic IP network connection (optional).

You can optionally configure TCP/IP after you have completed your z/VM installation. The TCP/IP configuration created in this step provides only a basic IP network connection for your z/VM host. In addition, this configuration is suitable for installations that employ only static (as opposed to dynamic) network routes.

Note: The IP configuration wizard supports real network devices only. If you plan on using virtual network devices for TCP/IP, they must be configured manually. See *z/VM: TCP/IP Planning and Customization*.

If you choose to configure a basic IP network connection for your z/VM host at this time, continue with this step. Otherwise, go to “Step 2. Back up the Named Saved Systems and Segments to Tape” on page 134.

For details about any DTCIPW messages you might receive while running IPWIZARD, see *z/VM: TCP/IP Messages and Codes*.

To establish a TCP/IP configuration that provides more comprehensive TCP/IP services, after you have completed your z/VM installation, see *z/VM: TCP/IP Planning and Customization*.

If you are going to use *z/VM: Getting Started with Linux on System z* to set up your Linux images, skip this step and go to “Step 2. Back up the Named Saved Systems and Segments to Tape” on page 134.

If you came to this step from *z/VM: Getting Started with Linux on System z*, continue with this step and then return to *z/VM: Getting Started with Linux on System z*.

Perform the following steps to configure TCP/IP for an initial network connection.

1. Gather the information from the TCP/IP configuration worksheet (Table 2 on page 8 or Table 10 on page 65).
2. Access minidisk 193.

```
access 193 e
Ready; T=n.nn/n.nn hh:mm:ss
```

3. Run IPWIZARD.

```
ipwizard
```

Configure TCP/IP for an Initial Network Connection

```
*** z/VM TCP/IP Configuration Wizard ***

The items that follow describe your z/VM host.

User ID of VM TCP/IP stack virtual machine: TCPIP__

Host name: _____
Domain name: _____

Gateway IP address: _____

DNS IP Addresses:
1) _____
2) _____
3) _____
:
:
PF1 = HELP PF3 = QUIT PF8 = Continue ENTER = Refresh
```

4. Using the information you gathered in the TCP/IP configuration worksheet (Table 2 on page 8 or Table 10 on page 65), fill in the z/VM TCP/IP Configuration Wizard panel and press F8 to continue.
5. Fill in the General Interface Configuration Panel and press F8 to continue. The panel content will depend on whether IPv4 or IPv6 is to be used.
6. Fill in the Interface Configuration Panel and press F5 to process. The panel content will depend on which interface type is to be used.
7. IPWIZARD attempts to create the TCP/IP configuration files. If the TCPIP user ID is logged on, IPWIZARD asks if you want to restart TCP/IP and continue processing.

```
DTCIPW2508I DTCIPWIZ EXEC is attempting to create the necessary
DTCIPW2508I configuration files
The TCP/IP stack (TCPIP) must be restarted as part of this procedure. Would
you like to restart TCPIP and continue?
Enter 0 (No), 1 (Yes)
```

If you continue, IPWIZARD tests the information you provided and returns any errors that occurred. If no errors are encountered, TCP/IP configuration files containing the network information you provided are created. For additional information on configuring TCP/IP, see *z/VM: TCP/IP Planning and Customization*.

Step 2. Back up the Named Saved Systems and Segments to Tape

In this step, you will:

- Back up all the named saved systems and segments, including CMS, to tape.

1. Attach a tape drive (*tapeaddr*) to MAINT at virtual device address 181.

```
attach tapeaddr * 181
TAPE 0181 ATTACHED
Ready; T=n.nn/n.nn hh:mm:ss
```

2. Mount a tape, to be used for back up, on the tape drive attached at virtual device address 181.
3. Spool the console.

```
spool console * start
```

4. Enter the SPXTAPE command to dump the named saved systems and segments to tape.

```
spxtape dump tapeaddr sdf all run
SPXTAPE DUMP INITIATED ON VDEV tapeaddr
Ready; T=n.nn/n.nn hh:mm:ss
```

The operand RUN specifies that the SPXTAPE rewinds and unloads the tape after the operation.

tapeaddr

Address of the tape drive attached to MAINT.

```
DUMPING tapeaddr :      nnn FILES, PAGES      nnnn nn% COMPLETE
:
```

```
DUMPING tapeaddr :      nnn FILES, PAGES      nnnn nn% COMPLETE
```

```
RDR FILE fileno1 SENT FROM MAINT CON WAS fileno1 RECS nnnn CPY 001 T NOHOLD NOKEEP
```

```
SPXTAPE DUMP COMMAND COMPLETED ON VDEV tapeaddr
```

```
TIME STARTED:      hh:mm:ss
```

The messages from SPXTAPE tell you that the files are being dumped to tape.

```
TIME ENDED:      hh:mm:ss
```

```
TAPE COUNT:      nnn
```

```
FILES PROCESSED:      nnn
```

```
SPOOL PAGES:      nnnn
```

```
RDR FILE fileno2 SENT FROM MAINT CON WAS fileno2 RECS nnnn CPY 001 T NOHOLD NOKEEP
```

fileno1

File number of the volume log file. The volume log file records information about the files processed by the SPXTAPE DUMP command that are associated with a particular tape volume.

fileno2

File number of the command summary log file. The command summary log file records the progress and status of the SPXTAPE DUMP operation.

5. Store the tape for emergency use. If it is ever necessary, you can use this tape and the SPXTAPE command to restore the CMS system data file. For more information about the SPXTAPE command, see *z/VM: CP Commands and Utilities Reference*. For information on how to restore this tape to your system, see Appendix F, "Restore the Named Saved Systems and Segments from Tape," on page 207.

Step 3. Back up the z/VM System to Tape

In this step, you will:

- Load the DDRXA utility to tape.
- Use DDRXA to back up the z/VM system to tape.

Notes:

1. A complete z/VM system backup includes all of your installation volumes.
2. You should check your installation worksheet to make sure you have backed up each volume.
3. This procedure requires a full pack minidisk be defined in the CP directory, USER DIRECT, for each volume you are backing up.
4. If you do not have a tape drive or if you wish to back up to DASD, see “Step 4. Back up the z/VM System to DASD” on page 138.

1. Attach a tape drive (*tapeaddr*) to MAINT at virtual device address 181.

```
attach tapeaddr * 181
TAPE 0181 ATTACHED
Ready; T=n.nn/n.nn hh:mm:ss
```

2. Mount a tape, to be used for back up, on the tape drive attached at virtual device address 181.
3. Access the 193 minidisk in read/write mode.

```
access 193 z
Ready; T=n.nn/n.nn hh:mm:ss
```

4. Load the DDRXA utility to tape.

```
utility utiltape ddrxa
Rewind complete
HCPWUT8317I MOVING IPL DDRXA TO TAPE
HCPWUT8318I THE IPL DDRXA PROGRAM IS
                ON TAPE FILE NUMBER 1
Ready; T=n.nn/n.nn hh:mm:ss
```

5. Rewind the scratch tape on virtual device number 181.

```
rewind 181
Rewind complete
```

6. IPL the tape and answer the prompts from DDRXA. For information about DDRXA, see the *z/VM: CP Commands and Utilities Reference* and *z/VM: System Operation*.

```
ipl 181 clear
z/VM DASD DUMP/RESTORE PROGRAM
ENTER CARD READER ADDRESS OR CONTROL STATEMENTS
ENTER:
```

CLEAR is necessary. Do not omit it.

Wait a few moments for DDRXA to prompt you. If a prompt does not appear, press Enter.

```
sysprint cons
ENTER:
```

This first control statement tells DDRXA that you want program messages sent to your console.

8. Press Enter to end the program.

ENTER

END OF JOB

9. IPL CMS again.

```
#cp ip1 cms  
z/VM V6.1.0   yyyy-mm-dd hh:mm
```

ENTER

Ready; T=*n.nn/n.nn hh:mm:ss*

For information on how to restore your system from tape, see Appendix G, “Restore the z/VM System Backup from Tape,” on page 209.

Step 4. Back up the z/VM System to DASD

In this step, you will:

- Use DDR to store a backup of the z/VM system to DASD.

Notes:

1. A complete z/VM system backup includes all of your installation volumes.
 2. You should check your installation worksheet to make sure you have backed up each installation volume.
 3. This procedure requires a full pack minidisk be defined in the CP directory, USER DIRECT, for each volume you are backing up.
 4. If you wish to store a back up to tape, see “Step 3. Back up the z/VM System to Tape” on page 135.
1. If you have already stored a backup of your z/VM system on tape, skip to “Step 5. Create an IPLable DDR Utility Tape” on page 140.
 2. Access the 193 minidisk in read/write mode.


```
access 193 z
Ready; T=n.nn/n.nn hh:mm:ss
```
 3. Run DDR and answer the prompts. For information about DDR, see the *z/VM: CP Commands and Utilities Reference* and *z/VM: System Operation*.

```
DDR
z/VM DASD DUMP/RESTORE PROGRAM
ENTER CARD READER ADDRESS OR CONTROL STATEMENTS
ENTER:
```

```
sysprint cons
ENTER:
```

```
input devno dasd valid
ENTER:
```

```
output devno dasd scratch
ENTER:
```

This first control statement tells DDR that you want program messages sent to your console.

The second control statement is the input control statement.

You must back up all your installation volumes, except the paging volume.

The full pack minidisk addresses for the default DASD are 122 (610SPL), 123 (610RES), 124 (610W01), 125 (610W02),

devno

Full pack minidisk address of the volume you are backing up.

valid

Volume label; for example 610RES.

You need a separate volume for each volume you are backing up.

devno

Full pack minidisk address of the volume you are using to backup.

Step 5. Create an IPLable DDR Utility Tape

You can optionally create an IPLable DDR utility tape. This tape can be used to IPL DDR stand-alone if you need to run DDR when CMS (and the DDR Module) is not available. If you choose to create the IPLable DDR utility tape, continue with this step. Otherwise, go to “Step 6. Create an IPLable ICKDSF Utility Tape” on page 141.

1. Attach a tape drive (*tapeaddr*) to MAINT at virtual device address 181.

```
attach tapeaddr * 181
TAPE 0181 ATTACHED
Ready; T=n.nn/n.nn hh:mm:ss
```

2. Mount a tape, to be used for the IPLable DDR utility, on the tape drive attached at virtual device address 181.
3. Access the 193 minidisk in read/write mode.

```
access 193 z
Ready; T=n.nn/n.nn hh:mm:ss
```

4. Load the DDRXA utility to tape.

```
utility utiltape ddrxa
Rewind complete
HCPWUT8317I MOVING IPL DDRXA TO TAPE
HCPWUT8318I THE IPL DDRXA PROGRAM IS
                ON TAPE FILE NUMBER 1
Ready; T=n.nn/n.nn hh:mm:ss
```

5. Rewind the scratch tape on virtual device number 181.

```
rewind 181
Rewind complete
```

6. IPL the tape and answer the prompts from DDRXA to verify the tape contents. For information about DDRXA, see *z/VM: CP Commands and Utilities Reference* and *z/VM: System Operation*.

```
ipl 181 clear
```

CLEAR is necessary. Do not omit it.

```
z/VM DASD DUMP/RESTORE PROGRAM
ENTER CARD READER ADDRESS OR CONTROL STATEMENTS
ENTER:
```

Wait a few moments for DDRXA to prompt you. If a prompt does not appear, press Enter.
This message verifies that IPLable DDRXA has been written to the tape.

7. IPL CMS.

```
#cp ipl cms
z/VM V6.1.0   yyyy-mm-dd hh:mm
```

```
ENTER
```

```
Ready; T=n.nn/n.nn hh:mm:ss
```

8. Rewind the tape and store for future use.

```
tape run
```

Step 6. Create an IPLable ICKDSF Utility Tape

You can optionally create an IPLable ICKDSF utility tape. This tape can be used to IPL ICKDSF stand-alone if you need to run ICKDSF when the ICKDSF module is not available. If you choose to create the IPLable ICKDSF utility tape, continue with this step. Otherwise, go to “Step 7. Create a Stand-alone Dump Tape” on page 143.

1. Attach a tape drive (*tapeaddr*) to MAINT at virtual device address 181.

```
attach tapeaddr * 181
TAPE      0181 ATTACHED
Ready; T=n.nn/n.nn hh:mm:ss
```

2. Mount a tape, to be used for the IPLable ICKDSF utility, on the tape drive attached at virtual device address 181.
3. Access the 193 minidisk in read/write mode.

```
access 193 z
Ready; T=n.nn/n.nn hh:mm:ss
```

4. Load the ICKDSF utility to tape.

```
utility utiltape dsf
Rewind complete
HCPWUT8317I MOVING IPL ICKDSF TO TAPE
HCPWUT8318I THE IPL ICKDSF PROGRAM IS
                ON TAPE FILE NUMBER 1
Ready; T=n.nn/n.nn hh:mm:ss
```

5. Rewind the scratch tape on virtual device number 181.

```
rewind 181
Rewind complete
```

6. IPL the tape and answer the prompts from ICKDSF to verify the tape contents. For information about ICKDSF, see *Device Support Facilities: User's Guide and Reference*.

```
ipl 181 clear
```

CLEAR is necessary. Do not omit it.

```
ICK005E DEFINE INPUT DEVICE, REPLY
        'DDDD, CUU' OR 'CONSOLE'
ENTER INPUT/COMMAND:
```

Wait a few moments for ICKDSF to prompt you. If a prompt does not appear, press Enter.

This message tells you that the Device Support Facilities (ICKDSF) is loaded and ready.

```
console
CONSOLE
ICK006E DEFINE OUTPUT DEVICE, REPLY
        'DDDD, CUU' or 'CONSOLE'
ENTER INPUT/COMMAND:
```

```
console
CONSOLE
ICK006E DEFINE OUTPUT DEVICE, REPLY
        'DDDD, CUU' or 'CONSOLE'
ENTER INPUT/COMMAND:
```

Create an IPLable ICKDSF Utility Tape

7. IPL CMS.

```
#cp ip1 cms  
z/VM V6.1.0   yyyy-mm-dd hh:mm
```

ENTER

```
Ready; T=n.nn/n.nn hh:mm:ss
```

8. Rewind the tape and store for future use.

```
tape run
```

Step 7. Create a Stand-alone Dump Tape

z/VM includes a stand-alone dump utility that you tailor according to your installation's configuration, using CMS. After you generate z/VM, you should create the stand-alone dump utility and place it on tape or a DASD for emergency use. If, after a system failure, CP cannot create an abend dump, you can use the stand-alone dump on tape or DASD to dump all of storage.

For instructions on creating a stand-alone dump utility on tape, see chapter 13 in *z/VM: CP Planning and Administration*.

Note: Do not use a stand alone dump tape or DASD created from a previous release of z/VM to attempt to dump your V6.1 system. When the HCPSADMP utility asks if you want to create a new HCPSDC MODULE, be sure to answer YES to create a new one for V6.1.

Create a stand-alone dump tape

Chapter 9. Plan Your Migration

In this chapter, you will:

- Gain an understanding for planning your migration.
- Review migration requirements.
- Complete migration worksheets.

Migration Overview

Rather than starting from scratch when you upgrade from your current system, you probably want to transfer and adjust your current information for use on the new system. Migration is the transfer and adjustment of information required to upgrade from one release to another.

Information you might want to transfer includes:

- Customized files
- Local modifications
- Service
- User-created files
- Saved segment definitions
- Spool files
- User directory entries
- SFS file pool servers
- Application programs

The z/VM migration procedure automates the transfer of the following types of files from the current to new system:

- Customized files as defined in the product's migration part table (*prodid MIGPvrm*)
- Local modifications for all products
- Service for products that are at the same release level in the new z/VM deliverable
- User-created files that reside on selected disks as defined in the product's migration disks table (*prodid MIGDvrm*)

During the migration process, you will be informed of additional actions required to complete migration (such as reworking local modifications and customized parts) to reconcile differences between the two releases.

Additional tasks must be performed after this procedure completes in order to migrate the following:

- Parm disks
- User directory
- Networking and connectivity
- Segments
- Spool space
- Security manager databases
- Directory manager databases
- Products and databases not preinstalled on the z/VM installation media.

For more information, see *z/VM: Migration Guide* and product-specific program directories.

Step 1. Review and Comply with the Requirements

Restriction: The z/VM migration procedure supports only the components and products that comprise the z/VM deliverable and can be used only to transfer files from a V5.2 or later system. The procedure should be run immediately after completing your installation, prior to enabling or customizing any components on the new system. If you are not going to use this procedure or do not satisfy this restriction, skip to Chapter 13, “Preinstalled Licensed Products and Features,” on page 179.

1. To use this migration procedure you must meet these requirements on your first-level V5.2 or later system (referred to as your current system).
 - General
 - Each customizable file must reside on the disk specified for that part in the product documentation.
 - Unless specifically documented to do otherwise, the VMSES/E local modification procedures must have been used to customize any IBM-supplied parts. The VMSES/E LOCALMOD command, which simplifies creation and reworking of local modifications, has been provided with past releases of z/VM to assist with such changes.
 - If you use a storage management tool (for example DFSMS™) you need to make sure that the auto-recall function is turned on so that stored files are available before running these procedures.
 - Have not removed any user IDs, minidisks, products, or components shipped with z/VM.
 - PPFs
 - The variable labels in the DCL section of a product’s PPF must not be changed.
 - If you have changed a user ID, minidisk address, or SFS directory definition you must override all PPFs that contain the user ID, minidisk address, or SFS directory.
 - If you created PPF overrides for the preinstalled components, products or features of z/VM, then you must override the P2P component in the SERVP2P \$PPF file. Your PPF override names must be in the VM SYSSUF software inventory file.
 - If any preinstalled products reside in SFS on your current system.
 - A TSAF collection will be used to allow file pool access.
 - If the user ID TSAFVM is running (either online or disconnected), then it will be used for the TSAF collection. If it is not running you will be prompted for a user ID to use for the TSAF collection.
 - The TSAF collection user ID must have a 191 minidisk, accessed as file mode A. An SFS directory cannot be used.
2. Requirements for the user ID on your current system where you will run these procedures.
 - The user ID must be MAINT or a user ID with privilege classes and authorizations equivalent to MAINT.
 - The VMSES/E software inventory disk needs to be linked (default is 51D).
 - The user ID must have a 191 minidisk, accessed as file mode A. An SFS directory cannot be used.
 - If any preinstalled products reside in SFS, the user ID must have SFS administration authority to all file pools that contains these products. Use the command `QUERY ENROLL ADMIN filepool` to determine which userids are enrolled as administrators for filepool *filepool*.
3. Considerations for the V6.1 system (referred to as your new system).
 - The new system must be running second level on the current system in order to run the migration tools.
 - If you have increased the size of any disk shipped on the z/VM installation media on the current system (unless instructed to do so by IBM Service), you might need to increase the size of that disk on the new system before migration.

Review and Comply with the Requirements

- Do not make any changes to your new system before using these migration procedures other than applying an RSU. Do not customize servers or file pools. Do not customize files or enable products or features on the new system before you use this migration procedure. The one exception is customizing files using the IPWIZARD.
4. To maintain migration compliance and be able to use the z/VM migration procedure in the future:
- Always use the VMSES/E local modification procedures to alter, modify or customize any IBM-supplied parts, unless it is specifically documented to do otherwise. The LOCALMOD command, which simplifies the creation and reworking of local modifications, is supplied with VMSES/E to assist with making such changes.
 - If you want to use an IBM-supplied SFS for your own data, use VMSYSU. Do not use VMSYS or VMSYSR.
 - Additional minidisks should not be defined on the DASD volumes used for the installation defined packs. The default labels for:
 - z/VM V5.2 are 520RES, 520W01, and 520W02.
 - z/VM V5.3 are 530RES, 530W01, and 530W02.
 - z/VM V5.4 are 540RES, 540W01, and 540W02.
 - z/VM V6.1 are 610RES, 610W01, and 610W02.

Step 2. Complete the Migration Worksheet

1. Record the addresses of your V6.1 DASD.
2. Select the current system user ID you will use to run these procedures. Verify that this user ID meets the following requirements:
 - The user ID must be MAINT or a user ID with privilege classes and authorizations equivalent to MAINT
 - The user ID must have a 191 minidisk, accessed as file mode A. An SFS directory cannot be used.
 - If any preinstalled products reside in SFS on your current system, the first-level user ID must have SFS administration authority to all file pools that contain these products.
3. If no preinstalled products reside in SFS on your current system, record *no* in the table and skip to substep 4. Otherwise record *yes* and complete the SFS section of the Migration Table
4. If you use a storage management tool, record a *yes* in the table and complete the auto-recall question; otherwise record *no* in the table

Table 16. Migration Worksheet

V6.1 System DASD Addresses _____		
Current system user ID you will use to run these procedures	_____	
SFS questions:		
Preinstalled products reside in SFS (yes or no)	_____	If yes, answer the remaining SFS questions.
TSAF collection user ID	_____	
TSAF user ID has a 191 (A) on minidisk not in SFS (yes or no)	_____	If no, a 191 disk must be defined before continuing.
Additional questions:		
Do you use a storage management tool? (yes or no)	_____	
If yes, is the auto-recall function turned on so that stored files are available? (yes or no)	_____	If no, the function must be turned on before continuing

Complete the migration worksheet

Chapter 10. Set Up for Migration

In this chapter, you will:

- IPL the new z/VM V6.1 system.
- Run MIGSETUP.
- Run MIGLINK.

Step 1. IPL the new z/VM System

1. Make sure you have completed the migration worksheet (Table 16 on page 149) and reviewed all requirements listed in Chapter 9, "Plan Your Migration," on page 145
2. Log on to the current system user ID you selected to use for the migration procedures.
3. Verify the user ID has met the migration requirements listed in Chapter 9, "Plan Your Migration," Step 1. Review and Comply with the Requirements, substep 2 on page 147.

4. Attach the DASD used to install the new z/VM V6.1 system.

Enter the following ATTACH command for each DASD listed in the migration worksheet:

```
attach dasdaddr *  
DASD dasdaddr ATTACHED TO userID dasdaddr  
:  
:  
Ready; T=n.nn/n.nn hh:mm:ss
```

5. IPL the new z/VM V6.1 system.

- a. Reset your virtual machine and make sure the z/VM system will recognize your terminal as a 3277, 3278, or 3279.

```
system clear  
Storage cleared - system reset.
```

```
terminal conmode 3270
```

- b. Verify you have 64 MB of virtual storage. If you have less than 64 MB of virtual storage, issue the DEFINE command to set your virtual storage to 64 MB.

```
query virtual storage  
STORAGE = nnnnM
```

```
define storage 64M  
STORAGE = 64M  
Storage cleared - system reset
```

- c. Set the virtual machine mode to ESA.

```
set machine esa
```

- d. Query the console to determine the virtual console address (*consaddr*). This address is required in the next substep.

```
query console  
CONS consaddr ON LDEV nnnn TERM START  
consaddr CL T NOCONT NOHOLD COPY 001 READY FORM STDN  
consaddr TO userID dev DIST nnnn FLASHC 000 DEST OFF  
consaddr FLASH CHAR MDFY 0 FCB LPP OFF  
consaddr 3270 NOEOF OPEN nnnn NOKEEP NOMSG NONAME  
consaddr SUBCHANNEL = nnnn
```

e. IPL the new z/VM system that was loaded to 610RES.

```
ipl dasdaddr clear loadparm consaddr
```

CLEAR is necessary. Do not omit it.

dasdaddr

Address of the system residence device (610RES).

consaddr

Virtual console address determined in substep 5d on page 152.

The Stand Alone Program Loader panel displays after issuing the IPL command.

```
STAND ALONE PROGRAM LOADER: z/VM VERSION 6 RELEASE 1.0
DEVICE NUMBER:  dasdaddr  MINIDISK OFFSET:  nnnnnnnn  EXTENT:  1
MODULE NAME:    CPLOAD    LOAD ORIGIN:      1000
-----IPL PARAMETERS-----
cons=consaddr
-----COMMENTS-----
-----
9= FILELIST  10= LOAD  11= TOGGLE EXTENT/OFFSET
```

Figure 13. Sample Stand Alone Program Loader Panel

f. Move the cursor to the IPL PARAMETERS field and enter:

```
cons=consaddr
```

consaddr

Virtual console address. Spaces are not allowed around the equal sign.

IPL the new z/VM system

g. Press F10 to load.

F10

```
hh:mm:ss z/VM V6 R1.0
        SERVICE LEVEL nnnn (64-BIT)

hh:mm:ss SYSTEM NUCLEUS CREATED ON yyyy-mm-dd AT hh:mm:ss,
        LOADED FROM 610RES
hh:mm:ss *****
hh:mm:ss * LICENSED MATERIALS - PROPERTY OF IBM* *
hh:mm:ss * 5741-A07 (C) COPYRIGHT IBM CORP. 1983, *
hh:mm:ss * 2009. ALL RIGHTS RESERVED. *
hh:mm:ss * US GOVERNMENT USERS RESTRICTED RIGHTS - *
hh:mm:ss * USE, DUPLICATION OR DISCLOSURE *
hh:mm:ss * RESTRICTED BY GSA ADP SCHEDULE CONTRACT *
hh:mm:ss * WITH IBM CORP. *
hh:mm:ss * *
hh:mm:ss * * TRADEMARK OF INTERNATIONAL BUSINESS *
hh:mm:ss * * MACHINES *
hh:mm:ss *****
hh:mm:ss HCPZC06718I Using parm disk 1 on volume 610RES (device xxxx).
hh:mm:ss HCPZC06718I Parm disk resides on cylinders xxx through xxx.
```

:

You might receive an informational message, HCPIIS951I, about volumes not mounted. If you are not using those volume labels, ignore this message.

Attention: If you receive informational message HCPIIS954I, you have duplicate volumes with the same label. You must return to the first-level CP environment (enter SHUTDOWN at the next prompt) and detach the duplicate volumes. Then return to substep 5a on page 152.

```
hh:mm:ss Start ((Warm|Force|COLD|CLEAN) (DRain)
        (Disable) (NODIRect) (NOAUTOlog)) or (SHUTDOWN)
```

force noautolog

```
NOW hh:mm:ss {EST|EDT} weekday yyyy-mm-dd
Change TOD clock (yes|no)
no
```

CP logs on the primary system operator user ID (OPERATOR).

```
hh:mm:ss The directory on volume 610RES at address nnnn
        has been brought online.
hh:mm:ss HCPWRS2513I
hh:mm:ss HCPWRS2513I Spool files available nnnn
hh:mm:ss HCPWRS2512I Spooling initialization is complete.
hh:mm:ss DASD nnnn dump unit CP IPL pages nnnn
hh:mm:ss HCPAAU2700I System gateway ZVMV6R10 identified.
hh:mm:ss z/VM Version 6 Release 1.0, Service Level 0000 (64-bit),
built on IBM Virtualization Technology
hh:mm:ss There is no logmsg data
hh:mm:ss FILES: NO RDR, NO PRT, NO PUN
hh:mm:ss LOGON AT hh:mm:ss EDT DAY mm/dd/yy
hh:mm:ss GRAF nnnn LOGON AS OPERATOR USERS = n
hh:mm:ss HCPIOP952I nnnnM system storage
hh:mm:ss FILES: nnnnnnnn RDR, nnnnnnnn PRT, NO PUN
hh:mm:ss HCPCRC8082I Accounting records are accumulating for userid DISKACNT
```

- h. Disconnect from the OPERATOR user ID.

disconnect

DISCONNECT AT *hh:mm:ss timezone weekday mm/dd/yy*

Press enter or clear key to continue

ENTER

- i. Log on as MAINT.

logon maint

The default password for MAINT is MAINT.

z/VM Version 6 Release 1.0, Service Level *nnnn* (64-bit),

built on IBM Virtualization Technology

There is no logmsg data

FILES: *nnnn* RDR, *nnnn* PRT, *nnnn* PUN

LOGON AT *hh:mm:ss timezone weekday mm/dd/yy*

z/VM V6 R1.0 *yyyy-mm-dd hh:mm*

ENTER

Ready; T=*n.nn/n.nn hh:mm:ss*

Run MIGSETUP

Step 2. Run MIGSETUP

1. Run MIGSETUP to copy migration tools to the 191 disk of your current system user ID. If you receive any error messages during MIGSETUP processing, look up the message in *z/VM: CP Messages and Codes*, take the appropriate action, and run the command again.

```
access 193 c  
DMSACC724I 193 replaces C(2CC)  
Ready;
```

```
migsetup  
HCPMSU8392I MIGSETUP EXEC ENDED SUCCESSFULLY  
Ready;
```

2. Shut down the V6.1 system.

```
shutdown  
SYSTEM SHUTDOWN STARTED  
HCPWRP963I STARTING SHUTDOWN STEP ..... - .....  
:  
HCPWRP963I STARTING SHUTDOWN STEP ..... - .....  
  
HCPWRP962I VM SHUTDOWN COMPLETED IN n SEC  
HCPWRP963I STARTING SHUTDOWN STEP SVADV - DEACTIVATE TERMINATION SAVE AREAS  
HCPWRP961W SYSTEM SHUTDOWN COMPLETE  
HCPGIR450W CP entered; disabled wait PSW 00020000 00000000 00000000 00000961
```

3. IPL CMS on your current system user ID.

```
ipl cms  
z/VM Vn.n.0
```

```
ENTER  
Ready;
```

Step 3. Run MIGLINK

1. Access the VMSES/E system inventory disk.

```
access 51D d
Ready; T=n.nn/n.nn hh:mm:ss
```

2. Run MIGLINK to establish the appropriate minidisk or SFS environment on your current system. If you receive any error messages during MIGLINK processing, look up the message in *z/VM: CP Messages and Codes*, take the appropriate action, and run the command again.

miglink

(You get the following prompt only if products reside in SFS on your current system)

```
HCPMLK8309R A TSAF COLLECTION NEEDS TO BE ESTABLISHED.
ONLY ONE TSAF COLLECTION CAN BE ACTIVE AT A
TIME. IF TSAF IS CURRENTLY RUNNING ON A
USERID DIFFERENT THAN 'TSAFVM' YOU NEED TO
ENTER THAT USERID.
ENTER:
```

```
0 TO QUIT
1 TO USE TSAFVM
OR
YOUR TSAF USERID
```

```
{ 0 | 1 | userID}
```

```
HCPMLK8392I MIGLINK EXEC ENDED SUCCESSFULLY
Ready;
```

Note: If you logoff your current system user ID at this point, when you log back on, you must attach your new system DASD and run MIGLINK again to establish your environment.

Step 4. IPL the new z/VM System

1. Reset your virtual machine and make sure the z/VM system will recognize your terminal as a 3277, 3278, or 3279.

```
system clear  
Storage cleared - system reset.
```

```
terminal conmode 3270
```

2. Verify you have 64 MB of virtual storage. If you have less than 64 MB of virtual storage, issue the DEFINE command to set your virtual storage to 64 MB.

```
query virtual storage  
STORAGE = nnnnM
```

```
define storage 64M  
STORAGE = 64M  
Storage cleared - system reset
```

3. Set the virtual machine mode to ESA.

```
set machine esa
```

4. Query the console to determine the virtual console address (*consaddr*). This address is required in the next substep.

```
query console  
CONS consaddr ON LDEV nnnn TERM START  
consaddr CL T NOCONT NOHOLD COPY 001 READY FORM STDN  
consaddr TO userID dev DIST nnnn FLASHC 000 DEST OFF  
consaddr FLASH CHAR MDFY 0 FCB LPP OFF  
consaddr 3270 NOEOF OPEN nnnn NOKEEP NOMSG NONAME  
consaddr SUBCHANNEL = nnnn
```

5. IPL the new z/VM system that was loaded to 610RES.

```
ipl dasdaddr clear loadparm consaddr
```

CLEAR is necessary. Do not omit it.

dasdaddr

Address of the system residence device
(610RES).

consaddr

Virtual console address determined in substep 4.

The Stand Alone Program Loader panel displays after issuing the IPL command.


```

STAND ALONE PROGRAM LOADER: z/VM VERSION 6 RELEASE 1.0

DEVICE NUMBER:  dasdaddr  MINIDISK OFFSET:  nnnnnnnn  EXTENT:  1
MODULE NAME:     CLOAD    LOAD ORIGIN:      1000

-----IPL PARAMETERS-----
cons=consaddr

-----COMMENTS-----

9= FILELIST  10= LOAD  11= TOGGLE EXTENT/OFFSET

```

Figure 14. Sample Stand Alone Program Loader Panel

6. Move the cursor to the IPL PARAMETERS field and enter:

```
cons=consaddr
```

```
consaddr
```

Virtual console address. Spaces are not allowed around the equal sign.

7. Press F10 to load.

F10

```

hh:mm:ss z/VM V6 R1.0
          SERVICE LEVEL nnnn (64-BIT)

hh:mm:ss SYSTEM NUCLEUS CREATED ON yyyy-mm-dd AT hh:mm:ss,
          LOADED FROM 610RES

hh:mm:ss *****
hh:mm:ss * LICENSED MATERIALS - PROPERTY OF IBM* *
hh:mm:ss * 5741-A07 (C) COPYRIGHT IBM CORP. 1983, *
hh:mm:ss * 2009. ALL RIGHTS RESERVED. *
hh:mm:ss * US GOVERNMENT USERS RESTRICTED RIGHTS - *
hh:mm:ss * USE, DUPLICATION OR DISCLOSURE *
hh:mm:ss * RESTRICTED BY GSA ADP SCHEDULE CONTRACT *
hh:mm:ss * WITH IBM CORP. *
hh:mm:ss * *
hh:mm:ss * * TRADEMARK OF INTERNATIONAL BUSINESS *
hh:mm:ss * MACHINES *
hh:mm:ss *****
hh:mm:ss HCPZC06718I Using parm disk 1 on volume 610RES (device xxxx).
hh:mm:ss HCPZC06718I Parm disk resides on cylinders xxx through xxx.
          :

```

You might receive an informational message, HCPIIS951I, about volumes not mounted. If you are not using those volume labels, ignore this message.

Attention: If you receive informational message HCPIIS954I, you have duplicate volumes with the same label. You must return to the first-level CP environment (enter SHUTDOWN at the next prompt) and detach the duplicate volumes. Then return to substep 1 on page 158.

```

hh:mm:ss Start ((Warm|Force|COLD|CLEAN) (DRain)
          (DIsable) (NODIRect) (NOAUTOlog)) or (SHUTDOWN)

```

IPL the new z/VM system

force drain noautolog

Use NOAUTOLOG because you cannot have the servers and all user IDs logged on.

```
NOW hh:mm:ss {EST|EDT} weekday yyyy-mm-dd
Change TOD clock (yes|no)
no
```

CP logs on the primary system operator user ID (OPERATOR).

```
hh:mm:ss The directory on volume 610RES at address nnnn
        has been brought online.
hh:mm:ss HCPWRS2513I
hh:mm:ss HCPWRS2513I Spool files available nnnn
hh:mm:ss HCPWRS2512I Spooling initialization is complete.
hh:mm:ss DASD nnnn dump unit CP IPL pages nnnn
hh:mm:ss HCPAAU2700I System gateway ZVMV6R10 identified.
hh:mm:ss z/VM Version 6 Release 1.0, Service Level 0000 (64-bit),
built on IBM Virtualization Technology
hh:mm:ss There is no logmsg data
hh:mm:ss FILES: NO RDR, NO PRT, NO PUN
hh:mm:ss LOGON AT hh:mm:ss EDT DAY mm/dd/yy
hh:mm:ss GRAF nnnn LOGON AS OPERATOR USERS = n
hh:mm:ss HCPIOP952I nnnnM system storage
hh:mm:ss FILES: nnnnnnnn RDR, nnnnnnnn PRT, NO PUN
hh:mm:ss HCPCRC8082I Accounting records are accumulating for userid DISKACNT
```

8. Disconnect from the OPERATOR user ID.

disconnect

```
DISCONNECT AT hh:mm:ss timezone weekday mm/dd/yy
```

Press enter or clear key to continue

ENTER

9. Log on as MAINT.

logon maint

The default password for MAINT is MAINT.

```
z/VM Version 6 Release 1.0 Service Level 0000 (64-bit),
built on IBM Virtualization Technolog
There is no logmsg data
FILES: nnnn RDR, NO PRT, NO PUN
LOGON AT hh:mm:ss timezone weekday mm/dd/yy
```

ENTER

Ready; T=n.nn/n.nn hh:mm:ss

Chapter 11. Migrate

In this chapter, you will:

- Run MIGRATE.
- View the MIGRATE message log.

Run MIGRATE

Step 1. Run MIGRATE

Run MIGRATE to move minidisk and shared file data for all preinstalled products.

```
migrate all vrm  
Ready;
```

vrm

Current version, release, and modification level you are migrating from. For example, if you are migrating from V5.2, enter 520.

Messages received from MIGRATE are logged in the \$VMFMIG \$MSGLOG file.

If you receive a return code of zero, skip to Chapter 12, “Place Migrated Parts into Production,” on page 165. Otherwise, continue with “Step 2. View the MIGRATE Message Log” on page 163.

Step 2. View the MIGRATE Message Log

View the MIGRATE message log and handle any nonzero return codes. Base your actions on the following table:

If you received . . .	Then . . .
Return code 4	<ol style="list-style-type: none"> <li data-bbox="609 373 1469 520">1. Issue VMFVIEW MIGRATE. You can ignore any warning messages that appear in the notes below. Take appropriate action based on other warning messages you receive. Messages are documented in <i>z/VM: Other Components Messages and Codes</i> or by issuing HELP on the message number. <li data-bbox="609 520 1469 562">2. Go to Chapter 12, "Place Migrated Parts into Production," on page 165.
Return code 6	<ol style="list-style-type: none"> <li data-bbox="609 583 1469 730">1. Issue VMFVIEW MIGRATE. You can ignore any warning messages that appear in the notes below. Take appropriate action based on other warning messages you receive. Messages are documented in <i>z/VM: Other Components Messages and Codes</i> or by issuing HELP on the message number. For messages VMFMGR2308I and VMFSUI2308W for CP local modification 99999, simply mark them reworked with the VMFUPDAT SYSLMOD command. <li data-bbox="609 730 1469 877">2. Use the VMFUPDAT SYSLMOD command to see which customized parts and local modifications you need to rework. Rework the customized parts and local modifications that were identified. For more information, see <i>z/VM: VMSES/E Introduction and Reference</i>. <li data-bbox="609 877 1469 940">3. After you complete the rework, use the VMFUPDAT SYSLMOD command to flag the customized parts and local modification as REWORKED. <li data-bbox="609 940 1469 1081">4. Return to "Step 1. Run MIGRATE" on page 162 and reissue the MIGRATE ALL command.
A return code greater than 6	<ol style="list-style-type: none"> <li data-bbox="609 1102 1469 1249">1. Issue VMFVIEW MIGRATE and check for warning and error messages. You can ignore any warning messages in the notes below. Take appropriate action based on other warning messages you receive. Messages are documented in <i>z/VM: Other Components Messages and Codes</i> or by issuing HELP on the message number. <li data-bbox="609 1249 1469 1291">2. Correct all errors reported in the error messages. <li data-bbox="609 1291 1469 1339">3. Return to "Step 1. Run MIGRATE" on page 162 and reissue the MIGRATE ALL command.

Note: You can ignore the following messages and their associated VMF1966W message:

- DMSLI0201W The following names are undefined: ISPLINK ARIPRDI
- DMSLI0201W The following names are undefined: DMSDSCSC
- DMSLI0201W The following names are undefined: DMSUSRX1 DMSUSRX2
- DMSLI0202W Duplicate identifier messages associated with object IOACMAIN MODULE.
- DMSLKD004W Warning messages issued messages associated with objects ILBONBL, ILBONTR, ILBOREC, ILBORNT, ILBOSND, ILBOSNT, and ILBOSSN.
- DMSLI0994W Restrictive RMODE encountered in CSECT CEEM@VOU
- DMSLI0994W Restrictive RMODE encountered in CSECT CEEBLIIA

View the MIGRATE message log

Chapter 12. Place Migrated Parts into Production

In this chapter, you will:

- Run PUT2PROD, MIGCLEAN, and MIGR51D.

Run PUT2PROD

Step 1. Run PUT2PROD

1. Log on as MAINT.

```
logon maint
:
Ready; T=n.nn/n.nn hh:mm:ss
```

The default password for MAINT is MAINT.

2. IPL CMS.

```
ipl cms
z/VM V6.1.0   yyyy-mm-dd hh:mm
```

ENTER

```
Ready; T=n.nn/n.nn hh:mm:ss
```

3. Run PUT2PROD.

```
put2prod
VMFP2P2760I PUT2PROD processing started
:
VMFP2P2760I PUT2PROD processing completed successfully
Ready; T=n.nn/n.nn hh:mm:ss
```

4. Handle a nonzero return code. Base your action on the following table:

If you received . . .	Then . . .
Return code 4	<ul style="list-style-type: none">• Issue VMFVIEW PUT2PROD. You can ignore any warning messages in the notes below. Take appropriate action based on other warning messages you receive.
A return code greater than 4	<ol style="list-style-type: none">1. Issue VMFVIEW PUT2PROD and check for warning and error messages.2. You can ignore any warning messages in the notes below. Take appropriate action based on other warning messages you receive.3. Correct all errors reported in the error messages.4. Issue IPL CMS.5. Issue PUT2PROD.6. If you receive a nonzero return code, repeat substep 4.

Note: You can ignore the following:

- DMSDCS1083E Saved segment \$\$DMY\$\$ does not exist
- DMSWLG292W Text data will be loaded at '20000'x in user area; user data may be overwritten.

Step 2. Shut Down the new System

1. Shut down the system.

```
shutdown
SYSTEM SHUTDOWN STARTED

HCPWRP963I STARTING SHUTDOWN STEP ..... - .....
:
:
HCPWRP963I STARTING SHUTDOWN STEP ..... - .....

HCPWRP962I VM SHUTDOWN COMPLETED IN nn SEC
HCPWRP963I STARTING SHUTDOWN STEP SVADV - DEACTIVATE TERMINATION SAVE AREAS
HCPWRP961W SYSTEM SHUTDOWN COMPLETE
HCPGIR450W CP entered; disabled wait PSW 00020000 00000000 00000000 00000961
```

2. IPL CMS on your current system user ID.

```
ipl cms
z/VM Vn.n.0   yyyy-mm-dd hh:mm
```

```
ENTER
```

```
Ready;
```

Run MIGCLEAN

Step 3. Run MIGCLEAN

Run MIGCLEAN to establish your original minidisk and SFS environment.

If you receive any error messages during MIGCLEAN processing, look up the message in *z/VM: CP Messages and Codes*, take the appropriate action, and run the command again.

```
migclean  
HCPMCL8392I MIGCLEAN EXEC ENDED SUCCESSFULLY  
Ready;
```

Step 4. Access Current System Software Inventory Disk

1. Access to the current system software inventory (SI) disk is required. Link the SI disk if it is not.

```
link maint 51d 51d rr  
Ready; T=n.nn/n.nn hh:mm:ss
```

The default owner and disk address are MAINT and 51D. If your SI disk has a different user ID or address, substitute that user ID and address for MAINT and 51D respectively.

2. Your current SI disk must be defined as address FFF for a future step in the migration procedures.

```
define 51D FFF  
DASD 0FFF DEFINED  
Ready; T=n.nn/n.nn hh:mm:ss
```

If your SI disk has an address other than 51D, substitute that disk address for 51D.

Step 5. IPL the new System

1. Reset your virtual machine and make sure the z/VM system will recognize your terminal as a 3277, 3278, or 3279.

```
system clear  
Storage cleared - system reset.
```

```
terminal conmode 3270
```

2. Verify you have 64 MB of virtual storage. If you have less than 64 MB of virtual storage, issue the DEFINE command to set your virtual storage to 64 MB.

```
query virtual storage  
STORAGE = nnnnM
```

```
define storage 64M  
STORAGE = 64M  
Storage cleared - system reset
```

3. Set the virtual machine mode to ESA.

```
set machine esa
```

4. Query the console to determine the virtual console address (*consaddr*). This address is required in the next substep.

```
query console  
CONS consaddr ON LDEV nnnn TERM START  
consaddr CL T NOCONT NOHOLD COPY 001 READY FORM STDN  
consaddr TO userID dev DIST nnnn FLASHC 000 DEST OFF  
consaddr FLASH CHAR MDFY 0 FCB LPP OFF  
consaddr 3270 NOEOF OPEN nnnn NOKEEP NOMSG NONAME  
consaddr SUBCHANNEL = nnnn
```

5. IPL the new z/VM system that was loaded to 610RES.

```
ipl dasdaddr clear loadparm consaddr
```

CLEAR is necessary. Do not omit it.

dasdaddr

Address of the system residence device
(610RES).

consaddr

Virtual console address determined in substep 4.

The Stand Alone Program Loader panel displays after issuing the IPL command.

```

STAND ALONE PROGRAM LOADER: z/VM VERSION 6 RELEASE 1.0

DEVICE NUMBER:  dasdaddr  MINIDISK OFFSET:  nnnnnnnn  EXTENT:  1
MODULE NAME:     CLOAD    LOAD ORIGIN:      1000

-----IPL PARAMETERS-----
cons=consaddr

-----COMMENTS-----

-----

9= FILELIST  10= LOAD  11= TOGGLE EXTENT/OFFSET

```

Figure 15. Sample Stand Alone Program Loader Panel

6. Move the cursor to the IPL PARAMETERS field and enter:

```
cons=consaddr
```

```
consaddr
```

Virtual console address determined in substep 4 on page 170. Spaces are not allowed around the equal sign.

7. Press F10 to load.

F10

```

hh:mm:ss z/VM V6 R1.0
          SERVICE LEVEL nnnn (64-BIT)

hh:mm:ss SYSTEM NUCLEUS CREATED ON yyyy-mm-dd AT hh:mm:ss,
          LOADED FROM 610RES

hh:mm:ss *****
hh:mm:ss * LICENSED MATERIALS - PROPERTY OF IBM* *
hh:mm:ss * 5741-A07 (C) COPYRIGHT IBM CORP. 1983, *
hh:mm:ss * 2009. ALL RIGHTS RESERVED. *
hh:mm:ss * US GOVERNMENT USERS RESTRICTED RIGHTS - *
hh:mm:ss * USE, DUPLICATION OR DISCLOSURE *
hh:mm:ss * RESTRICTED BY GSA ADP SCHEDULE CONTRACT *
hh:mm:ss * WITH IBM CORP. *
hh:mm:ss * *
hh:mm:ss * * TRADEMARK OF INTERNATIONAL BUSINESS *
hh:mm:ss * * MACHINES *
hh:mm:ss *****
hh:mm:ss HCPZC06718I Using parm disk 1 on volume 610RES (device xxxx).
hh:mm:ss HCPZC06718I Parm disk resides on cylinders xxx through xxx.
          :

```

You might receive an informational message, HCPIIS951I, about volumes not mounted. If you are not using those volume labels, ignore this message.

Attention: If you receive informational message HCPIIS954I, you have duplicate volumes with the same label. You must return to the first-level CP environment (enter SHUTDOWN at the next prompt) and detach the duplicate volumes. Then return to substep 1 on page 170.

IPL the new system

```
hh:mm:ss Start ((Warm|Force|COLD|CLEAN) (DRain)
              (DISable) (NODIRect) (NOAUTOlog)) or (SHUTDOWN)
```

force drain

```
NOW hh:mm:ss {EST|EDT} weekday yyyy-mm-dd
Change TOD clock (yes|no)
```

no

CP logs on the primary system operator user ID (OPERATOR).

```
hh:mm:ss The directory on volume 610RES at address nnnn
          has been brought online.
hh:mm:ss HCPWRS2513I
hh:mm:ss HCPWRS2513I Spool files available nnnn
hh:mm:ss HCPWRS2512I Spooling initialization is complete.
hh:mm:ss DASD nnnn dump unit CP IPL pages nnnn
hh:mm:ss HCPAAU2700I System gateway ZVMV6R10 identified.
hh:mm:ss z/VM Version 6 Release 1.0, Service Level 0000 (64-bit),
built on IBM Virtualization Technology
hh:mm:ss There is no logmsg data
hh:mm:ss FILES: NO RDR, NO PRT, NO PUN
hh:mm:ss LOGON AT hh:mm:ss EDT DAY mm/dd/yy
hh:mm:ss GRAF nnnn LOGON AS OPERATOR USERS = n
hh:mm:ss HCPIOP952I nnnnM system storage
hh:mm:ss FILES: nnnnnnnn RDR, nnnnnnnn PRT, NO PUN
hh:mm:ss HCPCRC8082I Accounting records are accumulating for userid DISKACNT
```

8. Disconnect from the OPERATOR user ID.

disconnect

```
DISCONNECT AT hh:mm:ss timezone weekday mm/dd/yy
```

Press enter or clear key to continue

ENTER

Step 6. Run MIGR51D

In this step, you will:

- Migrate your 51D disk from your current system.

1. Log on as MAINT.

```
logon maint
```

The default password for MAINT is MAINT.

```
z/VM Version 6 Release 1.0 Service Level 0000 (64-bit)
built on IBB Virtualization Technology
There is no logmsg data
FILES: nnn RDR, NO PRT, NO PUN
LOGON AT hh:mm:ss timezone weekday mm/dd/yy
```

```
ENTER
```

```
Ready; T=n.nn/n.nn hh:mm:ss
```

2. Create a backup copy of the your new system software inventory (SI) disk (default is 51D) using your site's normal backup procedures.
3. Access the SI disk (defined on your current system user ID as FFF) from your current system.

```
attach FFF *
```

```
Ready; T=n.nn/n.nn hh:mm:ss
```

```
access FFF z
```

```
Ready; T=n.nn/n.nn hh:mm:ss
```

4. Access the new system 51D minidisk as file mode D.

```
access 51D d
```

```
Ready; T=n.nn/n.nn hh:mm:ss
```

5. Access the 493 minidisk as file mode W.

```
access 493 w
```

```
Ready; T=n.nn/n.nn hh:mm:ss
```

6. Use MIGR51D to update the system SI files.

```
migr51d
```

```
HCPMIX8478R Please enter filemode letter of the
Software Inventory Disk (51D) from
the previous release. Press enter
to Exit.
```

```
z
```

The VM Software Inventory Disk (51D) Product and Segment Migration panel is displayed.

Run MIGR51D

```
*** VM Software Inventory Disk (51D) Product Migration ***

Set action code AC to D = Do Not Migrate or to M = Migrate product. Action
code I means product is already installed on new 51D and cannot be migrated.

AC Compname      Prodid  Status  Description
-----
D SHELL          2VMVMZ30 APPLIED Shell and Utilities for VM/ESA
                2.3.0
M DITTO          5654029C NONE   DITTO/ESA VM 1.2.0
D
D                5735NFSQ ENABLED
D CMS            5VMCMS20 BUILT   CMS component for z/VM 5.2.0
D CP             5VMCPR20 BUILT   CP component for z/VM 5.2.0
D TCP/IP        5VMTCP20 BUILT   TCP/IP LEVEL 520 - TCP/IP Feature
I ICKDSF         5684042J BUILT   ICKDSF DEVICE SUPPORT FACILITIES
                R17 for CMS

Page 1 of 1

PF1=HELP PF3/PF12=Quit PF5=Process PF8=Forward
```

- a. Enter an action code (AC) for each product listed. For information about the panel and action codes, press F1.

Notes:

- 1) This Product Migration panel is only a sample. Your panels will not list the same products, action codes, status, and description.
 - 2) Products that are preselected as **D** (Do Not Migrate) should not be changed.
 - 3) If a product is not supported on the new z/VM release, you should enter **D** (Do Not Migrate) for that product.
 - 4) Before you delete any product, you must determine whether any product that you intend to migrate is dependent on this product. You can use VMFINFO or VMFSIM SYSDEP to determine product dependencies.
- b. Press F8 to select action codes for all Software Inventory Migration panels before continuing to the next step.
- c. Press F5 to process the product migration information and display the Segment Migration panel. Depending on the size of your software inventory files, it may take several minutes to process.


```

*** VM Software Inventory Disk (51D) Segment Migration ***

Set action code AC to D = Do Not Migrate or to M = Migrate segment. Action
code P means segment will be migrated due to product migration. If =====
or ***** appears under Segname, enter a new name to change the segment
name upon migration ( ===== Must be changed, ***** May be changed ).

AC Segname      ProdId  Compname      Defparms      Bldparms
-----
D  CMSBAM      01d-> 5VMCMS20 CMS      B0D-B37 SR    PPF(ESA)
      New-> 6VMCMS10 CMS      B0D-B37 SR    PPF(ZVM)
      ***** Mig-> 6VMCMS10 CMS      B0D-B37 SR    PPF(ZVM)
D  CMSDOS      01d-> 5VMCMS20 CMS      B00-B0C SR    PPF(ESA)
      New-> 6VMCMS10 CMS      B00-B0C SR    PPF(ZVM)
      ***** Mig-> 6VMCMS10 CMS      B00-B0C SR    PPF(ZVM)
D  CMSFILES    01d-> 5VMCMS20 CMS      1900-1BFF SR  PPF(ESA)
      New-> 6VMCMS10 CMS      1900-1BFF SR  PPF(ZVM)
      ***** Mig-> 6VMCMS10 CMS      1900-1BFF SR  PPF(ZVM)
D  CMSPIPES    01d-> 5VMCMS20 CMS      1800-18FF SR  PPF(ESA)
      New-> 6VMCMS10 CMS      1800-18FF SR  PPF(ZVM)
      ***** Mig-> 6VMCMS10 CMS      1800-18FF SR  PPF(ZVM)
                                           Page 1 of 4

PF1=HELP PF3/PF12=Quit PF5=Process PF8=Forward

```

- d. Enter an action code for each segment listed. For information about the panel and action codes, press F1.
This Segment Migration panel is only a sample. Your panels will not list the same segments, action codes, status, and description.
 - e. Press F8 to select action codes for all Software Inventory Segment Migration panels before continuing to the next step.
 - f. Press F5 to process. Depending on the size of your SI files, it may take several minutes to process.
7. MIGR51D updated the V6.1 VMSES/E system SI files on your new 51D disk to reflect the licensed products installed on your old system that you chose to migrate. You must now migrate all code, user IDs, minidisks, and segments associated with each licensed product reflected in the new system software inventory files. See the documentation for each licensed product for information on the code, user IDs, minidisks, and segments required.

If the licensed product segments are built by VMSES/E, you must sign on to any one of the licensed product installation user IDs, or MAINT, and enter the following to update some of the other segment files on the system SI disk:

- a. Issue:

```
vmfsgmap segbld esasegs segblist
```

At this time, you can make further changes to any segment.

- b. On the first panel, enter:

```
segmerge
```

- C. Press F5 to save your changes and exit from VMFSGMAP.

The VMFSGMAP and SEGMERGE commands only need to be done once, from one user ID. At this point, the appropriate files on the system software inventory disk are updated.

Now you can use the VMFBLD command to build the licensed product segments from the corresponding licensed product installation user IDs. Follow the information in the licensed product program directories.

Run MIGR51D

For example:

```
vmfbld ppf segbld esasegs segblist myseg (serviced
```

To rebuild the CMS segments, see the “Using the COR Service Procedure” chapter of *z/VM: Service Guide*, and follow “Rebuild the Saved Segments” under the “Place Your Serviced Components into Production” step.

For example:

```
vmfbld list segbld esasegs zvmsegs blddata (serviced
```

Note: You need to rebuild the segments on the new system to get the SYSTEM SEGID file updated.

You have now completed the automated migration procedure.

Additional Information

Additional migration information that you should be aware of:

1. In addition to the customizable files that were moved from your current system to your new V6.1 system, some minidisks were migrated. When a minidisk is migrated, all of the files that exist on the minidisk on your current system that did NOT exist on the minidisk on your new system are copied to the minidisk on the new system. When these files are migrated, message VMFMGR1319W is included in the migration message log, \$VMFMIG \$MSGLOG.

The following are general guidelines for disk migration:

- Local and sample disks are migrated
 - Help disks are not migrated
 - Base disks are not migrated
 - PARM disks (MAINTs CF1, CF2, CF3) are not migrated
 - Apply and delta disks:
 - If the product on the new system is the same release as the current system (OSASF, ICKDSF), the apply and delta disks are migrated
 - If the product on the new system is a different release than the current system (CP/DV, CMS/REXX, DIRMAINT, GCS, LE, PERFTK, RACF, RSCS, TCPIP, TSAF/AVS, VMHCD, VMSES), the apply and delta disks are not migrated
 - DirMaint™ database disks are not migrated
 - RACF database disks are not migrated
2. Additional tasks must be performed after this procedure completes in order to migrate the following. See *z/VM: Migration Guide* and product-specific Program Directories for additional information on migration:
 - Parm disks
 - User directory
 - Networking and connectivity
 - Segments
 - Spool space
 - Security manager databases
 - Directory manager databases
 - Products and databases not preinstalled on the z/VM installation media

Additional Information

Chapter 13. Preinstalled Licensed Products and Features

Note: Some of the preinstalled product and features require additional installation steps. You must complete these steps for the product or feature to be completely installed.

The z/VM installation media was built incorporating the following licensed products and features.

Table 17. Preinstalled Licensed Products and Features

Product name	Release level	Program number	Is product or feature installed disabled or enabled?	Do I need to configure before using the product or feature?
Directory Maintenance Facility	6.1.0	5741-A07	Disabled ¹	Yes ²
EREP	3.5.0	5654-260	Enabled	No
HCD and HCM for z/VM	5.4.0	5741-A07	Enabled	No ³
ICKDSF	1.17.0	5684-042	Enabled	No
OSA/SF	4.4.0	5741-A07	Enabled	Yes ²
Performance Toolkit for VM	6.1.0	5741-A07	Disabled ¹	Yes ²
RACF Security Server for z/VM	6.1.0	5741-A07	Disabled ¹	Yes ²
RSCS Networking for z/VM	6.1.0	5741-A07	Disabled ¹	Yes ²
TCP/IP	6.1.0	5741-A07	Enabled	Yes ²

Notes:

1. This product or feature is not available for customer use unless you have a license for it. To use this product or feature, you must order it as documented in the appropriate program directory.
2. To use this product or feature, it must be configured. For configuration information, see the appropriate program directory.
3. This product can be customized.

For detailed information about a product or feature, see its own documentation. See the “Bibliography” on page 227.

Directory Maintenance Facility

Directory Maintenance Facility provides support for all the z/VM directory statements. DirMaint also provides additional utilities to help manage minidisk assignments and allocations, and provides a level of security regarding command authorizations and password monitoring.

Installation Instructions: The installation of DirMaint is complete. To use DirMaint, it must be enabled and configured. See section “6.0 Installation Instructions” in the Directory Maintenance Facility program directory.

Environmental Record Editing and Printing Program

The Environmental Record Editing and Printing Program (EREP) is a diagnostic application program that runs under the MVS™, VM, and VSE operating systems. The purpose of EREP is to help IBM service representatives maintain your data processing installations.

Installation Instructions: No additional installation instructions are required.

Hardware Configuration Definition and Hardware Configuration Manager for z/VM

Hardware Configuration Definition and Hardware Configuration Manager for z/VM (HCD and HCM for z/VM) provides a comprehensive I/O configuration management environment, similar to that available with the z/OS® operating system.

HCM runs on a Microsoft™ Windows-based personal computer connected to the z/VM system through a TCP/IP network connection. HCM provides a graphical user interface as well as commands to help you configure your system. You supply the needed I/O configuration information to HCM, which processes the information and passes it to HCD.

HCD runs in a z/VM server virtual machine and performs the work of actually creating and changing the hardware and software aspects of your I/O configuration. While HCM provides the primary user interface to HCD, HCD also provides a backup user interface on your z/VM host for certain I/O configuration tasks, in case HCM is not available.

z/VM's original dynamic I/O configuration capabilities are still valid. These consist of a set of system operator commands for changing the System z server's I/O configuration while the system continues to run, or for managing the hardware I/O configuration of all of the logical partitions in your System z server. You now have the choice of either using these commands or else using HCM and HCD to manage your I/O configuration. Note, however, that the use of HCM and HCD is incompatible with the original dynamic I/O configuration capabilities. You should select one method to use for the duration of any given IPL of your z/VM system.

Installation Instructions: The installation of the HCD host code is complete. To **install** the workstation code (user interface) and customize HCD, see section “6.0 Installation Instructions” in the Hardware Configuration Definition and Hardware Configuration Manager program directory and follow the installation instructions.

Device Support Facilities (ICKDSF)

Device Support Facilities (ICKDSF) is a program you can use to perform functions needed for the installation, use, and maintenance of IBM DASD. You can also use it to perform service functions, error detection, and media maintenance.

Installation Instructions: No additional installation instructions are required.

Open Systems Adapter Support Facility

Open Systems Adapter Support Facility (OSA/SF) lets you customize the integrated Open Systems Adapter (OSA) hardware feature for the OSA modes, change the settable OSA port parameters, and obtain status about the OSA.

OSA/SF has a Java-based interface, which is called the OSA/SF Graphical User Interface (OSA/SF GUI).

Through the System Authorization Facility (SAF) interface of the system image on which it is running, OSA/SF lets you use the RACF Security Server for z/VM (RACF), or equivalent, to authorize or deny access to OSA/SF commands.

Installation Instructions: The installation of the OSA/SF host code is complete. To **install** the workstation code (OSA/SF user interface) and configure OSA/SF, see section “6.0 Installation Instructions” in the Open Systems Adapter Support Facility program directory and follow the installation instructions.

Performance Toolkit for VM

Performance Toolkit for VM provides performance management capabilities for VM systems. It is a performance analysis tool for z/VM systems that can be used to detect and diagnose performance problems, analyze system performance, and provide printed reports that show the utilization and response times of key system components. You can also use Performance Toolkit for VM to improve operator efficiency and productivity.

Installation Instructions: The installation of Performance Toolkit for VM is complete. To use Performance Toolkit for VM, it must be enabled and configured. See section “6.0 Installation Instructions” in Performance Toolkit for VM program directory.

RACF Security Server for z/VM

RACF Security Server for z/VM (RACF) is a product that works together with the existing system features of z/VM to provide improved data security for an installation.

Installation Instructions: The installation of RACF is complete. To use RACF, it must be enabled and configured. See section “6.0 Installation Instructions” in Resource Access Control Facility (RACF) Security Server program directory.

Remote Spooling Communications Subsystem (RSCS) Networking for z/VM

Remote Spooling Communications Subsystem (RSCS) Networking for z/VM lets users send messages, files and mail to coworkers at other systems on their TCP/IP, SNA, or non-SNA network. They can also use RSCS to print documents and issue commands on other systems.

RSCS uses z/VM spooling facilities to store and retrieve data. RSCS can transfer data to other systems (such as z/VM, z/OS, OS/400®, VSE/ESA™, UNIX®, Linux, and AIX/ESA®) that support Network Job Entry (NJE) protocols. NJE connectivity options include TCP/IP, SNA, ESCON®, channel to channel, and Binary Synchronous Communication.

RSCS also supports secure data transfer between z/VM spool and a system that is a workstation that supports Remote Job Entry (RJE) or Multileaving RJE (MRJE) protocols. RJE/MRJE connectivity options include SNA, and Binary Synchronous Communication.

RSCS provides the full range of all possible print service connectivity options. Instead of LPSERVE, the RSCS server may be chosen to provide an enhanced level of TCP/IP print support, including LPR and LPD. These services allow for intranet and internet print delivery for a system, and also accept print output from those networks. The ability to print data at a workstation printer in a transparent manner is available to end users regardless of how the printer is accessed.

The enhanced level of TCP/IP print support provided by RSCS (LPR, LPD, UFT, and TN3270E) may be used without obtaining a license for RSCS and enabling RSCS. All other RSCS features can only be used after obtaining a license and enabling RSCS.

Installation Instructions: The installation of RSCS is complete. To use RSCS, it must be enabled and configured. See section “6.0 Installation Instructions” in Remote Spooling Communications Subsystem (RSCS) Networking program directory.

Transmission Control Protocol/Internet Protocol for z/VM

Transmission Control Protocol/Internet Protocol for z/VM (TCP/IP) enables z/VM customers to participate in a multivendor, open networking environment using the TCP/IP protocol suite for communications and interoperability. The applications provided in TCP/IP include the ability to transfer files, send mail, log on a remote host, allow access from any other TCP/IP node in the network, and perform other network client and server functions.

Installation Instructions: The installation of TCP/IP is complete. To use TCP/IP, it must be configured. See section “6.0 Installation” in TCP/IP program directory for more information. If you used the IPWIZARD command to initially configure TCP/IP, additional modifications may be required depending on the needs of your installation.

Congratulations!

You have completed z/VM installation. Your system will need to be tailored and there are several planning and administration guides available to do so. See “Bibliography” on page 227.

Part 4, “Service Procedure,” on page 183 contains the procedures for servicing your system and should be used to apply service when required.

Return to the z/VM System Delivery Offering program directory when you are ready to install other licensed products.

Part 4. Service Procedure

In this part, you will:

- Run SERVICE to install preventive (recommended service upgrade–RSU) or corrective (COR) service.
- Run PUT2PROD to place the service into production.

The SERVICE EXEC automates the steps for installing preventive (RSU) and corrective (COR) service, while the PUT2PROD EXEC automates the steps for placing service into production. These EXECs apply to the following components, features, and products:

Table 18. Components, Features, and Products Supported by SERVICE and PUT2PROD

Product	COMPNAME
VMSES/E	VMSES
REXX™/VM	REXX
Language Environment	LE
CMS	CMS
CP	CP
GCS	GCS
Dump Viewing Facility	DV
TSAF	TSAF
AVS	AVS
RSCS Networking for z/VM	RSCS
TCP/IP	TCPIP
OSA/SF for VM	OSA
Directory Maintenance Facility	DIRM
RACF Security Server for z/VM	RACF
Performance Toolkit for VM	PERFTK
HCD and HCM for z/VM	VMHCD

Notes:

1. PUT2PROD cannot be used for products other than those listed in Table 18.
2. The steps that SERVICE and PUT2PROD automate are documented in *z/VM: Service Guide* and applicable product program directories.
3. For more information about SERVICE and PUT2PROD, see *z/VM: VMSES/E Introduction and Reference*.
4. For more information on using SERVICE to service VMSES/E-formatted program products that are not preinstalled as part of z/VM installation, see Appendix A, “Setting up VMSES/E Licensed Products to use SERVICE,” on page 193.

Chapter 14. Install Preventive (RSU) or Corrective (COR) Service and Place the Service into Production

In this chapter, you will:

- Run SERVICE to receive, apply, and build the preventive (RSU) or corrective (COR) service.
- Run PUT2PROD to place the products into production when you are satisfied with the service.

Step 1. Load the Service Files from the RSU or COR

In this step, you will:

- Run SERVICE to receive, apply, and build the preventive (RSU) or corrective (COR) service.

Note: SERVICE processes only one RSU or COR per invocation. It does, however, process all volumes of a multiple-volume RSU or COR in a single invocation.

1. Make sure you have a current backup of your system. For information about backing up your system, see “Step 3. Back up the z/VM System to Tape” on page 135 or “Step 4. Back up the z/VM System to DASD” on page 138.
2. Log on as MAINT.

```
ENTER
logon maint
:
z/VM V6.1.0    yyyy-mm-dd hh:mm
```

The default password for MAINT is MAINT.

```
ENTER
:
Ready; T=n.nn/n.nn hh:mm:ss
```

3. If the RSU or COR is on tape, continue with this substep. Otherwise, skip to substep 4 on page 187.
 - a. Attach a tape drive to MAINT as 181.

```
attach tapeaddr * 181
TAPE tapeaddr ATTACHED TO MAINT 181
Ready; T=n.nn/n.nn hh:mm:ss
```

- b. Mount volume 1 of your service tapes on your 181 tape drive. If you are using an automated tape library (ATL), see the automated tape library manuals.
If the RSU or COR has multiple volumes, either:
 - Stack the RSU or COR volumes on 181, or
 - Attach additional tape drives and mount each volume.

C. IPL CMS.

```
ipl cms
z/VM V6.1.0    yyyy-mm-dd hh:mm
```

```
ENTER
Ready; T=n.nn/n.nn hh:mm:ss
```

- d. If all the volumes are mounted on 181, run SERVICE with no parameters.

```
service
VMFSRV2760I SERVICE processing started
:
VMFSRV2760I SERVICE processing completed
successfully
Ready; T=n.nn/n.nn hh:mm:ss
```

Load the service files from the RSU or COR

- e. If the volumes are mounted on multiple tape drives, run SERVICE with the following parameters:

<code>service all tapeaddr1 tapeaddr2 ...</code>	List the addresses of each tape volume.
<code>VMFSRV2760I SERVICE processing started</code>	
<code>:</code>	<code>tapeaddr1</code>
<code>VMFSRV2760I SERVICE processing completed</code>	Tape address for tape volume 1
<code>successfully</code>	<code>tapeaddr2 ...</code>
<code>Ready; T=n.nn/n.nn hh:mm:ss</code>	Tape address for tape volume 2, and so on.

Go to substep 5.

4. If the RSU or COR service is electronic or CD-ROM, continue with this substep.
- a. Retrieve the entire RSU or COR service. (The MAINT 500 minidisk can be used to load the service files.)
- If your media is electronic, follow the instructions that were sent to you electronically.
 - If your media is CD-ROM, follow the instructions in the README file on the CD-ROM.

Note: You must preserve the file attribute of FIXED BINARY 1024 through all intermediary transports.

- b. IPL CMS.

```
ipl cms
z/VM V6.1.0    yyyy-mm-dd hh:mm
```

ENTER

```
Ready; T=n.nn/n.nn hh:mm:ss
```

- c. Access the minidisk containing the service files and decompress the VMSES/E envelope file.

```
access diskaddr c
Ready;
```

```
deterse envfn envft envfm = servlink =
```

You need to enter the DETERSE command for every envelope file you receive with your order.

- d. Run SERVICE against the COR documentation envelope file. This step is only for COR service as the RSU documentation envelope file is a text readable file.

```
service all docenvfn
```

`docenvfn`

File name of the documentation envelope.

```
vmfupdat systemo
```

Displays the memos that were in the documentation envelope

- e. Run SERVICE against PTF or RSU envelope.

```
service all envfn1 envfn2 ...
VMFSRV2760I SERVICE processing started
:
VMFSRV2760I SERVICE processing completed
successfully
Ready; T=n.nn/n.nn hh:mm:ss
```

List the file names of each PTF or RSU envelope. You can specify more than one envelope file only if the RSU or COR is multivolume.

`envfn1`

File name for the first envelope.

`envfn2 ...`

File name for the second envelope, and so on.

5. View the SERVICE messages log (VMFVIEW SERVICE) and handle any nonzero return codes. Base your actions on the following table:

Load the service files from the RSU or COR

If you received . . .	Then . . .
Return code 4	<ol style="list-style-type: none">1. Issue VMFVIEW SERVICE. You can ignore any warning messages in the notes below. Take appropriate action based on other warning messages you receive.2. Go to substep 6.
Return code 6 and the message: VMFSUII2760I VMFSUFIN PROCESSING INCOMPLETE DUE TO LOCAL MODIFCATIONS	<ol style="list-style-type: none">1. Issue VMFVIEW SERVICE. You can ignore any warning messages in the notes below. Take appropriate action based on other warning messages you receive.2. Use the VMFUPDAT SYSLMOD command to see which local modifications you need to rework. Rework the local modifications that were affected by service. For more information, see <i>z/VM: VMSES/E Introduction and Reference</i>.3. After you complete the rework, use the VMFUPDAT SYSLMOD command to flag the local modification as reworked.4. Restart by issuing SERVICE RESTART.5. If you receive a nonzero return code, repeat substep 5 on page 187.6. Go to substep 6.
A return code greater than 6	<ol style="list-style-type: none">1. Issue VMFVIEW SERVICE and check for warning and error messages.2. You can ignore any warning messages in the notes below. Take appropriate action based on other warning messages you receive.3. Correct all errors reported in the error messages.4. Restart by issuing the SERVICE command as displayed in the message VMFSRV2310W.5. If you receive a nonzero return code, repeat substep 5 on page 187.6. Go to substep 6.

Note: You can ignore the following messages and their associated VMF1966W message:

- DMSLI0201W The following names are undefined: ISPLINK ARIPRDI
- DMSLI0201W The following names are undefined: DMSDSCSC
- DMSLI0201W The following names are undefined: DMSUSRX1 DMSUSRX2
- DMSLI0202W Duplicate identifier messages associated with object IOACMAIN MODULE.
- DMSLKD004W Warning messages issued messages associated with objects ILBONBL, ILBONTR, ILBOREC, ILBORNT, ILBOSND, ILBOSNT, and ILBOSSN.
- DMSLI0994W Restrictive RMODE encountered in CSECT CEEM@VOU
- DMSLI0994W Restrictive RMODE encountered in CSECT CEEBLIIA

6. Use the VMFUPDAT SYSMEMO command to review any memos that were received with this service.

Step 2. Place the Service into Production

In this step, you will:

- Run PUT2PROD to place the products that were processed by SERVICE into production. Do this step only after you are satisfied with the service.

Attention:

1. PUT2PROD cannot be used for products other than those listed in Table 18 on page 183.
2. PUT2PROD will affect your production environment. It is recommended that all users be logged off. Placing service into production should be performed as part of a planned system outage. The following list of production environment virtual machines will be logged off to write to minidisks or SFS directories they own.

DATAMOVE	OSASF	RSCSDNS
DIRMAINT	OSAMAIN	TCPMAINT
DIRMSAT	RSCS	XCHANGE

3. If you are running RACF and you receive the message VMFP2P1219E while running PUT2PROD, you need to IPL the system using the CF2 PARM disk with NOAUTOLOG and then XAUTOLOG your backup RACF server machine, RACMAINT, before attempting to put RACF service into production. For more information, see the Resource Access Control Facility (RACF) Security Server program directory.

1. Log on as MAINT.

```

ENTER
logon maint
:
z/VM V6.1.0    yyyy-mm-dd hh:mm

ENTER
:
Ready; T=n.nn/n.nn hh:mm:ss

```

The default password for MAINT is MAINT.

2. IPL CMS.

```

ipl cms
z/VM V6.1.0    yyyy-mm-dd hh:mm

ENTER
Ready; T=n.nn/n.nn hh:mm:ss

```

3. Run PUT2PROD.

```

put2prod
VMFP2P2760I PUT2PROD processing started
:
VMFP2P2760I PUT2PROD processing completed successfully
Ready; T=n.nn/n.nn hh:mm:ss

```

4. If you received return code 0, skip this substep. Otherwise, handle a nonzero return code. Base your action on the following table:

Place the service into production

If you received . . .	Then . . .
Return code 4	<ol style="list-style-type: none">1. Issue VMFVIEW PUT2PROD. You can ignore any warning messages in the notes below. Take appropriate action based on other warning messages you receive.2. Go to substep 5.
A return code greater than 4	<ol style="list-style-type: none">1. Issue VMFVIEW PUT2PROD and check for warning and error messages.2. Take appropriate action based on warning messages.3. Correct all errors reported in the error messages.4. Issue IPL CMS.5. Issue PUT2PROD.6. If you receive a nonzero return code, repeat substep 4 on page 189.7. Go to substep 5.

Note: The following messages can be ignored:

- DMSDCS1083E Saved segment \$\$DMY\$\$ does not exist
- DMSWL292W Text data will be loaded at '20000'x in user area; user data may be overwritten.

5. Shut down and re-IPL the system.

```
shutdown reipl
```

```
ENTER
```

You have now complete the service procedure.

Part 5. Appendixes

Appendix A. Setting up VMSES/E Licensed Products to use SERVICE

You can use SERVICE to automate the apply, receive, and build service steps for installed VMSES/E licensed products that are not preinstalled on the z/VM system DDR. To use SERVICE on these products after you have installed them, you must update the System-Level Service Update Facility (VM SYSSUF) software inventory file by using the VMFUPDAT command, as follows.

For a list of the preinstalled products, see Table 18 on page 183.

Note: You cannot use PUT2PROD for VMSES/E licensed products that are not preinstalled on the z/VM system. Instead, see the steps for placing a product into production in that product's program directory.

Before you begin: You must have the software inventory disk accessed. By default, the software inventory disk is the 51D disk and it is accessed as D.

Perform the following steps to setting up the licensed products:

1. Log on as MAINT.

```
ENTER
logon maint
:
Ready; T=n.nn/n.nn hh:mm:ss
```

The default password for MAINT is MAINT.

2. Invoke VMFUPDAT to update the VM SYSSUF file.

```
vmfupdat syssuf
```

```
*** Update SYSSUF Table Entries ***

Update any PPF/component name or YES|NO field. To change all occurrences
of a PPF name in the table replace both ***** fields with PPF names.

Compname      Prodid  Servlev  Description
-----
ADSM          5654A09A  RSU-0101  ADSTAR Distributed Storage Manager for
:INSTALL    YES      :INSPPF  SERVP2P  ADSM
:BUILD      YES      :BLDPPF  SERVP2P  ADSM
:INCLUDE    YES      :P2PPPF  SERVP2P  ADSMP2P
AVS           6VMAVS10 000-0000  AVS for z/VM 6.1.0
:INSTALL    YES      :INSPPF  SERVP2P  AVS
:BUILD      YES      :BLDPPF  SERVP2P  AVS
:INCLUDE    YES      :P2PPPF  SERVP2P  AVSP2P
CMS           6VMCMS10 000-0000  CMS for z/VM 6.1.0
:INSTALL    YES      :INSPPF  SERVP2P  CMS
:BUILD      YES      :BLDPPF  SERVP2P  CMS
:INCLUDE    YES      :P2PPPF  SERVP2P  CMSP2P

Change PPF name ***** to *****

Page 1 of 9

PF1=HELP  PF3/PF12=Quit  PF5=Process  PF6=VMFSUFTB  PF8=Forward
```

3. Press F6 to refresh the VM SYSSUF table from the information on your system inventory disk (51D). This adds the new product(s) you installed in to the VM SYSSUF table and displays the table again.
4. Locate the product to be used with SERVICE by scrolling forward.

Example: In the following example, HLASM was added, then the user scrolled to it.

Setting up VMSES/E licensed products to use SERVICE

```
*** Update SYSSUF Table Entries ***

Update any PPF/component name or YES|NO field. To change all occurrences
of a PPF name in the table replace both ***** fields with PPF names.

Compname      Prodid  Servlev  Description
-----
HLASM          5696234E 000-0000 HIGH LEVEL ASSEMBLER FOR MVS & VM &
:INSTALL      YES      :INSPPF  5696234E HLASM
:BUILD        YES      :BLDPPF  5696234E HLASM
:INCLUDE      YES      :P2PPPF
ICKDSF        5684042J 011-0011 ICKDSF DEVICE SUPPORT FACILITIES R17
:INSTALL      YES      :INSPPF  SERVP2P ICKDSF
:BUILD        YES      :BLDPPF  SERVP2P ICKDSF
:INCLUDE      YES      :P2PPPF  SERVP2P ICKDSFP2P
LE            5VMLEN40 000-0000 IBM Language Environment for z/VM 4.4.0
:INSTALL      YES      :INSPPF  SERVP2P LE
:BUILD        YES      :BLDPPF  SERVP2P LE
:INCLUDE      YES      :P2PPPF  SERVP2P LEP2P

Change PPF name ***** to *****

Page 4 of 10

PF1=HELP PF3/PF12=Quit PF5=Process PF7=Backward PF8=Forward
```

5. If necessary, change the :INSPPF and :BLDPPF fields to the PPF name you are using to service this product.
6. Press F5 to process. The VM SYSSUF table is updated and you exit VMFUPDAT.

You have completed the update procedure. You can now use SERVICE to apply service for new product(s) you added. For more information on using SERVICE, see “Step 1. Load the Service Files from the RSU or COR” on page 186.

Appendix B. Determining the RSU Level for Ordering Service

Use the SERVICE command with the STATUS operand to determine the current RSU Service Level for a component or product. The SERVICE command queries the system-level service update facility (VM SYSSUF) table, which contains a list of all products or components that are installed on the system.

Before you begin: You must have the software inventory disk accessed. By default, the software inventory disk is the 51D disk and it is accessed as D.

To determine the RSU level of a component, issue the SERVICE command as follows:

```
service compname status
```

compname

A component defined in Table 18 on page 183 or any other component defined in the VM SYSSUF table.

Example: In this example, “0901” represents the RSU level that you would use when ordering service for CP.

```
VMFSRV2195I SERVICE CP STATUS
VMFSRV2760I SERVICE processing started
VMFSRV1225I CP (6VMCPRI0%CPSFS) status:
VMFSRV1225I   Service Level   RSU-0901
VMFSRV1225I   Production Level RSU-0901
VMFSRV2760I SERVICE processing completed successfully
```

For more information, see SERVICE EXEC in *z/VM: VMSES/E Introduction and Reference*.

Post z/VM System Installation

Appendix C. Migrate 51D from the Old System

You can use the MIGR51D command to migrate your current system inventory disk to your new system. If your current system is at least z/VM V5.2, you can do this as part of the migration procedure (documented in Chapter 9, “Plan Your Migration,” on page 145 through Chapter 12, “Place Migrated Parts into Production,” on page 165). If your current system is older than z/VM V5, or if you do not wish to follow the entire migration procedure, you can run MIGR51D as an independent activity.

To run MIGR51D as an independent activity, complete the steps listed here and then go to Chapter 12, “Place Migrated Parts into Production” and complete “Step 4. Access Current System Software Inventory Disk” on page 169 through “Step 6. Run MIGR51D” on page 173, as directed, in step 2 below.

1. Create a backup of the z/VM version 6 release 1 system software inventory (SI) disk (default is 51D) using your site’s normal backup procedures.
2. On your new system, obtain access to the system software inventory (SI) files (51D) on your current system.

If your new system can be IPLed as a second level system on your current system, then go to Chapter 12, “Place Migrated Parts into Production” and complete “Step 4. Access Current System Software Inventory Disk” on page 169 through “Step 6. Run MIGR51D” on page 173.

If your new system is running first level, see your system programmer for assistance in making a copy of the current system SI files accessible on your new system. On your new system, create a new minidisk on the MAINT userid, FFF, to store the SI files from your current system. Once the current system SI files are stored on minidisk FFF on your new system, go to Chapter 12, “Place Migrated Parts into Production,” “Step 6. Run MIGR51D” on page 173.

Migrate 51D from the old system

Appendix D. Apply or Rework Local Service and Modifications

You can use the LOCALMOD command to create and apply or rework local service and modifications to any component or product defined in the System-Level Service Update Facility (VM SYSSUF) software inventory table.

Apply or Create a Local Modification

You can use the LOCALMOD command to create and apply local modifications to any component or product defined in the System-Level Service Update Facility (VM SYSSUF) software inventory table.

Before you begin: You must have the software inventory disk accessed. By default, the software inventory disk is the 51D disk and it is accessed as D.

1. Create and apply the local modification.

a. Run LOCALMOD:

```
localmod compname partfn partft
```

compname

Component name associated with the product you are modifying (for example one of the COMPNAME values in Table 18 on page 183).

partfn

File name of the source part that is to be modified.

partft

File type of the source part that is to be modified.

b. Reply to any prompt messages.

c. Make your changes to the displayed file.

d. File your changes.

```
====> file
```

Enter **file** on the XEDIT command line.

e. Repeat this entire step for any additional local modifications that you need to make.

2. Run SERVICE, for each component processed, to build the local modification(s).

```
service compname build
```

3. Run PUT2PROD to put the local modification(s) into production.

```
put2prod
```

Note: You can use only PUT2PROD for products listed in Table 18 on page 183. If you have reworked a local modification for a product that you added to the VM SYSSUF table, follow that product's instructions (found in the product's program directory) to place its service into production.

Rework a Local Modification

You can use the LOCALMOD command to rework a local modification to any component or product defined in the System-Level Service Update Facility (VM SYSSUF) software inventory table.

Before you begin: You must have the software inventory disk accessed. By default, the software inventory disk is the 51D disk and it is accessed as D.

1. Rework the local modification.

a. Run LOCALMOD:

```
localmod compname partfn partft (rework
```

compname

Component name associated with the product you are reworking (for example one of the COMPNAME values in Table 18 on page 183).

partfn

File name of the source part that is to be reworked.

partft

File type of the source part that is to be reworked.

b. Reply to any prompt messages.

c. Make your changes to the displayed file.

d. File your changes.

```
====> file
```

Enter **file** on the XEDIT command line.

e. Repeat this entire step for any additional local modifications that you need to rework.

2. Run SERVICE, for each component processed, to build the local modification(s).

If you received a return code 6 (rework local modifications) from a SERVICE invocation, enter the following:

```
service restart
```

Otherwise, enter the following:

```
service compname build
```

3. Run PUT2PROD to put the local modification(s) into production.

```
put2prod
```

Note: You can use only PUT2PROD for products listed in Table 18 on page 183. If you have reworked a local modification for a product that you added to the VM SYSSUF table, follow that product's instructions (found in the product's program directory) to place its service into production.

Apply Local Service

You can use the LOCALMOD command to apply local service to any component or product defined in the System-Level Service Update Facility (VM SYSSUF) software inventory table. Local service is defined as any service received from IBM that is not on a COR or RSU tape (or envelope).

Before you begin: You must have the software inventory disk accessed. By default, the software inventory disk is the 51D disk and it is accessed as D.

1. Apply the local service.

a. Run LOCALMOD:

```
localmod compname partfn partft servfn servft
```

compname

Component name associated with the product you are modifying (for example one of the COMPNAME values in Table 18 on page 183).

partfn

File name of the part to be serviced.

partft

File type of the part to be serviced.

If the service is an update, *partft* is the file type of the service part, for example ASSEMBLE. If the service is a replacement part, *partft* is the file type of the part to be replaced, for example TEXT.

servfn

File name of the service received from IBM.

servft

File type of the service received from IBM.

b. Reply to any prompt messages.

c. Repeat this entire step for any additional local service.

2. Run SERVICE, for each component processed, to build the local service.

```
service compname build
```

3. Run PUT2PROD to put the local service into production.

```
put2prod
```

Note: You can use only PUT2PROD for products listed in Table 18 on page 183. If you have applied local service for a product that you added to the VM SYSSUF table, follow that product's instructions (found in the product's program directory) to place its service into production.

Apply Local Service

Appendix E. Contents of the z/VM System

Products Loaded from the z/VM System Installation Media

Products installed on the z/VM system are:

- z/VM
 - Control Program (CP)
 - Dump Viewing Facility (DV)
 - Conversational Monitor System (CMS)
 - REstructured eXtended eXecutor/VM (REXX)
 - Virtual Machine Serviceability Enhancements Staged/Extended (VMSES)
 - Group Control System (GCS)
 - Transparent Services Access Facility (TSAF)
 - APPC/VM VTAM[®] Support (AVS)
 - Language Environment (LE)
 - 3800 Model-3 Printer Image Library
 - UCENG Help - Uppercase English Help minidisk
 - Kanji Help - Japanese Help minidisk
- Environmental Record Editing and Printing Program (EREP)
- Device Support Facilities (ICKDSF)
- Remote Spooling Communications Subsystem (RSCS) Networking for z/VM
- Transmission Control Protocol/Internet Protocol (TCPIP)
- Open Systems Adapter Support Facility (OSA)
- Directory Maintenance Facility (DIRM)
- RACF Security Server for z/VM (RACF)
- Performance Toolkit for VM (PERFTK)
- Hardware Configuration Definition and Hardware Configuration Manager for z/VM (VMHCD)

CMS Defaults

The CMS nucleus was built with a local mod to DMSNGP. This local mod updates the CYLADDR, which defines where to write the CMS nucleus on the System disk (the recomp value).

CP Defaults

1. The LOGO CONFIG and SYSTEM CONFIG files are located on the primary parm disk (CF1). A shadow of these files resides on the secondary parm disk (CF2) and backup parm disk (CF3). These files contain the system configuration data used by CP.
2. For detailed information about the CP system configuration function, CP nucleus options, and CP planning, see *z/VM: CP Planning and Administration*.
3. The CP nucleus on the z/VM system is a module. The module resides on the parm disks (CF1, CF2, and CF3).
4. The CP nucleus is IPLed with the system default language, mixed case American English (AMENG), Uppercase English (UCENG), or Kanji (KANJI), which was selected during installation.
5. The USER DIRECT file on the MAINT 2CC minidisk contains entries defining each virtual machine (user) permitted to log on to your system.

CP defaults

If there is no machine mode defined for a user ID, the default machine mode definition is XA. However, issuing the SET MACHINE command overrides the default setting. The USER DIRECT file which was built during installation contains a SET MACHINE XA, SET MACHINE ESA, or SET MACHINE XC command for all user IDs.

- The USER DIRECT file contains a common profile section, PROFILE IBMDFLT. An INCLUDE statement for this profile has been added to each user ID that previously linked to the AMENG HELP disk (19D). The PROFILE IBMDFLT section contains a link to each HELP disk. Each user you add to the directory that needs access to a HELP disk must have an INCLUDE statement to the PROFILE IBMDFLT section or a LINK statement for each of the three help disks.
- The z/VM system contains system definition files with sample information and default parameters. You can modify the following files to define your system configuration.
 - The logo configuration file (LOGO CONFIG) defines both the logo that appears on your terminal screen when you log on your system and the logo that appears on separator pages for printers. This file also provides information to the system about status areas on the terminal screens.
Note: Status areas are normally in the lower right side of the terminal and contain such informational messages as RUNNING, VM READ, CP READ, MORE..., and HOLDING.
 - The CP system control file (SYSTEM CONFIG) describes the system residence device (610RES) and various system parameters, defining the configuration of your system.
- CP ships several CP Sample Utility Programs to help you configure your system once installation is complete. They are located on the MAINT 2C2 minidisk. For additional information on these programs, see appendix A in *z/VM: CP Planning and Administration*.

GCS Defaults

- The GCS nucleus was built with mixed case American English (AMENG) as the system default language.
- The GCS nucleus was built with a system name of GCS and is loaded at storage locations X'400'-X'5FF' and X'1000'-X'11FF'.
- The GCS nucleus was also built with the following defaults:

Default Item	Description
Saved System Name	GCS
Authorized VM User IDs	VTAM GCS MAINT NETVIEW OPERATNS RSCS AVSVM PDMREM1 PDMGRP4 SNALNKA PVMG NVAS IHVOPER CMEOSI NPM VSCS
Saved System Information	Recovery machine user ID: GCS User ID to receive storage dumps: OPERATNS GCS Trace Table Size: 16KB Common storage above 16MB line (YES or NO): YES Single user environment: no Maximum number of VM machines: 14 System ID: GCS Name of the VSAM segment: CMSVSAM Name of the BAM segment: CMSBAM GCS saved system is restricted: yes Trace table in private storage: yes
Saved System links	VTAM NETVSG00

User IDs needing VSAM storage

NETVIEW NVAS CMEOSI

Saved Segments on the z/VM System

1. CMS improves system performance and storage usage by placing heavily used execs in the CMS installation segment, CMSINST. CMSINST is a logical segment within the INSTSEG physical segment. If you want to add or delete an exec from CMSINST, you should identify the changes to VMSES/E using the procedure within the local modification example for CMSINST, see *z/VM: Service Guide*. A local modification allows VMSES/E to track the changes and to ensure the CMSINST segment is rebuilt when any of the execs in it are serviced.
2. The QUERY NSS ALL MAP command displays the saved segments and saved systems defined on your system. The segments might be displayed in a different order.

```
query nss all map
```

Enter the QUERY NSS ALL MAP command to list all defined saved segments and their addresses.

```

:
FILE FILENAME FILETYPE MINSIZE BEGPAG ENDPAG TYPE CL #USERS PARMREGS VMGROUP
nnnn ZCMS NSS 0000256K 00000 0000D EW A 00000 00-15 NO
00020 00023 EW
00F00 013FF SR
nnnn CMS NSS 0000256K 00000 0000D EW A 00000 00-15 NO
00020 00023 EW
00F00 013FF SR
nnnn GCS NSS 0000256K 00000 0000C EW R 00000 OMITTED YES
00400 0044E SR
0044F 0044F SW
00450 005FF SN
01000 0101A SR
0101B 011FF SN
nnnn CMSDOS DCSS-M N/A 00B00 00B0C SR A 00000 N/A N/A
nnnn CMSBAM DCSS-M N/A 00B0D 00B37 SR A 00000 N/A N/A
nnnn DOSBAM DCSS-S N/A 00B00 00B37 -- A 00000 N/A N/A
nnnn MONDCSS CPDCSS N/A 09000 09FFF SC R 00000 N/A N/A
nnnn GUICSLIB DCSS N/A 01F00 01FFF SR A 00000 N/A N/A
nnnn CMSFILES DCSS N/A 01900 01BFF SR A 00000 N/A N/A
nnnn SVM DCSS N/A 01900 019FF SR A 00000 N/A N/A
nnnn CMSPIPES DCSS N/A 01800 018FF SR A 00001 N/A N/A
nnnn CMSVMLIB DCSS N/A 01700 017FF SR A 00001 N/A N/A
nnnn INSTSEG DCSS N/A 01400 016FF SR A 00001 N/A N/A
nnnn HELPSEG DCSS N/A 00C00 00CFF SR A 00000 N/A N/A
nnnn PERFOUT DCSS N/A 08A00 08FFF SN A 00000 N/A N/A
nnnn DOSINST DCSS N/A 00900 0090F SR A 00000 N/A N/A
nnnn SCEE DCSS N/A 00900 009FF SR A 00000 N/A N/A
nnnn SCEEEX DCSS N/A 02100 028FF SR A 00000 N/A N/A
nnnn NLSKANJI DCSS N/A 02000 020FF SR A 00000 N/A N/A
nnnn NLSUCENG DCSS N/A 02000 020FF SR A 00000 N/A N/A
nnnn NLSAMENG DCSS N/A 02000 020FF SR A 00000 N/A N/A
Ready; T=n.nn/n.nn hh:mm:ss

```

VMSERVS, VMSERVU, and VMSERVER File Pool Defaults

The z/VM system incorporates three prebuilt file pools.

VMSYS

- Managed by the VMSERVS server machine
- Enrolled MAINT in the VMSYS file pool
- BFS directories defined for Shell and Utilities, and for SSL

VMSEVS, VMSEVU, and VMSEVR file pool defaults

Note: User IDs always enrolled in the VMSYS file pool are: GSKSSLDB, LDAPSRV, ROOT, SSLSERV, VMRMSVM, VSMPROXY, VSMREQIN, VSMREQUIU, VSMWORK1, VSMWORK2, and VSMWORK3.

VMSYSU

- Managed by the VMSEVU server machine
- Enrolled MAINT in the VMSYSU file pool
- MAINT.SAMPLES directory exists with SFS sample files installed.
- BFS directory, /ETC/gskadm/, defined for SSL

VMSYSR

- Managed by the VMSEVR server machine
- Coordinated resource recovery (CRR) file pool

Each of these file pools has two definition files associated with it:

- *filename* POOLDEF, which defines the configuration of the file pool. *filename* is the name of the file pool.
- *filename* DMSPARMS, which contains startup parameters for the file pool server machine. *filename* is the user ID of the server machine.

For more information and examples on tailoring these files and on BFS root directory definitions, see *z/VM: CMS File Pool Planning, Administration, and Operation*.

VMSYS File Pool

If you chose to load these products into the file pool, the following user IDs are also enrolled in the VMSYS file pool:

Table 19. VMSYS File Pool User Ids

Product	User ID(s)
RSCS	6VMRSC10 RSCSAUTH RSCSDNS XCHANGE
OSA/SF	4OSASF40 OSADMIN1 OSADMIN2 OSADMIN3 OSAMAIN OSASF
TCP/IP	6VMTCP10
ICKDSF	5684042J
DIRM	6VMDIR10
RACF	6VMRAC10
PERFTK	6VMPTK10 PERFSVM
VMHCD	5VMHCD40 CBDIODSP

Appendix F. Restore the Named Saved Systems and Segments from Tape

In this procedure, you will:

- Restore the CMS named saved system and segments.

You should have created a loadable tape of the named saved systems and segments during your system installation. Perform the following steps to restore the named saved system and segments.

1. Log on as MAINT.

```
ENTER
logon maint
:
:
Ready; T=n.nn/n.nn hh:mm:ss
```

The default password for MAINT is MAINT.

2. Attach a tape drive (*tapeaddr*) to MAINT.

```
attach tapeaddr *
Ready; T=n.nn/n.nn hh:mm:ss
```

3. Mount the backup tape on the attached tape drive (*tapeaddr*).
4. Spool the console.

```
spool console *
```

5. Enter the SPXTAPE command to load the system data files.

```
spxtape load tapeaddr sdf all run
                                     tapeaddr
                                     Address of the tape drive attached to MAINT.

SPXTAPE LOAD INITIATED ON VDEV tapeaddr
Ready; T=n.nn/n.nn hh:mm:ss

LOADING tapeaddr :      nnn FILES,  PAGES  nnnn
:
LOADING tapeaddr :      nnn FILES,  PAGES  nnnn
SPXTAPE LOAD END-OF-TAPE ON VDEV tapeaddr;
MOUNT NEXT TAPE
TAPE NUMBER:      tapeaddr-001
FILES PROCESSED:   nnn
SPOOL PAGES:      nnnn
LOADING tapeaddr :      nnn FILES,  PAGES  nnnn
:
LOADING tapeaddr :      nnn FILES,  PAGES  nnnn
RDR FILE fileno1 SENT FROM MAINT   CON WAS fileno RECS nnnn CPY 001 T NOHOLD NOKEEP
```

fileno1
File number of the volume log file.

The volume log file records information about the files processed by the SPXTAPE LOAD command that are associated with a particular tape volume.

Restore the named saved systems and segments from tape

6. When all volumes have been loaded, use the SPXTAPE END command to end the SPXTAPE load.

```
spxtape end tapeaddr
SPXTAPE END      INITIATED ON VDEV tapeaddr
SPXTAPE LOAD COMMAND ENDED      ON VDEV tapeaddr
TIME STARTED:      hh:mm:ss
TIME ENDED:        hh:mm:ss
TAPE COUNT:        nnn
FILES PROCESSED:   nnn
SPOOL PAGES:       nnnn
```

The SPXTAPE END command ends the SPXTAPE LOAD operation at the completion of the current file.

Ready; T=*n.nn/n.nn hh:mm:ss*

The CMS ready message may occur between the messages.

```
RDR FILE fileno2 SENT FROM MAINT      CON WAS fileno RECS nnnn CPY 001 T NOHOLD NOKEEP
```

fileno2
File number of the command summary log file.

The command summary log file records the progress and status of the SPXTAPE LOAD operation.

For more information on the SPXTAPE command, see *z/VM: CP Commands and Utilities Reference*.

7. IPL the CMS named saved system.

```
ipl cmsname
:
z/VM V6.1.0   yyy-mm-dd hh:mm
```

ENTER

Ready; T=*n.nn/n.nn hh:mm:ss*

cmsname
Either the IBM supplied system name (CMS) or the name you defined in DMSNGP on the SYSNAME statement.

If you have changed the version heading, your own heading will appear.

Appendix G. Restore the z/VM System Backup from Tape

In this procedure, you will:

- Restore the backup of your new z/VM system from tape.

Note: This procedure requires a full pack minidisk be defined in the CP directory, USER DIRECT, for each volume you are restoring.

You should have created a backup of your new z/VM system on tape during your system installation. Perform the following steps to restore the system.

1. Mount the backup tape on a tape drive.
2. Perform an IPL of the tape device.

```
ipl tapeaddr clear
```

tapeaddr

Address of the tape drive.

3. Use DDRXA to restore the system to disk. Repeat this substep for each DASD volume you are restoring.

```
z/VM DASD DUMP/RESTORE PROGRAM  
ENTER CARD READER ADDRESS OR CONTROL STATEMENTS  
ENTER:
```

```
sysprint cons  
ENTER:
```

This first control statement tells DDRXA that you want program messages sent to your console.

```
input tapeaddr tape  
ENTER:
```

The second control statement is the input control statement.

tapeaddr

Device number where the backup tape is mounted.

You can specify one alternate tape drive for additional tape volumes.

Example: If you had a tape attached to 181 and an alternate tape attached to 182, the INPUT control statement would be:

```
input 181 tape 182
```

If you are using a 3590 tape, and multiple DASD volumes were dumped on one tape volume, use the leave option to position the tape for the next restore. The input control statement would be:

```
input 181 tape (leave
```

Restore the z/VM system backup from tape

```
output devaddr dasd volid
ENTER:
```

This output statement specifies the DASD device to which you are restoring the system.

devaddr

Full-pack minidisk address of the volume to which you are restoring this tape.

The full-pack minidisk addresses for the default DASD are 122 (610SPL), 123 (610RES) 124 (610W01), 125 (610W02), ...

By typing **dasd**, the device type (3390) is automatically identified by the DDRXA program.

```
restore all
```

The RESTORE ALL statement tells DDRXA to restore the whole tape to the output device.

```
RESTORING volid
DATA DUMPED mm/dd/yy
  AT hh.mm.ss GMT FROM volid
  RESTORED TO volid
INPUT CYLINDER EXTENTS      OUTPUT CYLINDER EXTENTS
  START      STOP           START      STOP
  nnnnnnnn  nnnnnnnn      nnnnnnnn  nnnnnnnn
:
END OF RESTORE
BYTES RESTORED nnnnnnnnnn
```

Informational messages: GMT means Greenwich Mean Time.

The exact cylinder extents vary according to the device type.

Repeat INPUT, OUTPUT, and RESTORE statements for each DASD you are restoring.

```
ENTER:
:
```

When DDRXA finishes, it prompts you with ENTER. Press Enter to end the program.

```
ENTER:
```

```
ENTER
```

```
END OF JOB
```

Note: When DDRXA encounters the end of a tape, and there is more data to restore, the program prompts you to mount the next tape.

- If you are using the same tape drive, mount the next tape and DDRXA continues.
- If you are using an alternate tape drive, DDRXA uses the alternate tape drive, then alternates between the tape drives for additional tapes. That is, if there are more than two tapes, you are prompted for the third tape on the first tape drive, the fourth tape on the second tape drive, and so forth.

Appendix H. Recover a File or Minidisk

In this procedure, you will:

- Recover an entire minidisk. To recover a minidisk, you may either overlay the existing disk or restore the minidisk to a temporary disk and copy the files to the target disk.
- Recover an individual file from the installation media. To recover an individual file, you must first determine on which minidisk the file is located, restore the entire minidisk to a temporary disk, and copy the file from the temporary disk.

1. Log on as MAINT.

```
ENTER  
logon maint  
:  
Ready; T=n.nn/n.nn hh:mm:ss
```

The default password for MAINT is MAINT.

2. If you want to recover an entire minidisk, skip this substep and go to substep 3.

To recover an individual file, you must first determine on which minidisk the file is located. If you already know on which minidisk the file is located, go to substep 3. Otherwise, check the minidisk map file. If you loaded z/VM to the file pool, the minidisk map file is on the directory VMSYS:MAINT.CPDV.OBJECT. Access this directory in place of the 194 disk.

```
access 194 z  
Ready; T=n.nn/n.nn hh:mm:ss  
  
xedit minidisk map z  
:  
quit  
Ready; T=n.nn/n.nn hh:mm:ss
```

The MINIDISK MAP file lists the minidisks shipped on the z/VM system and the files contained on each minidisk. Look at MINIDISK MAP to determine which minidisk contains the file you want to recover.

3. If you want to recover an individual file or recover the entire minidisk to a temporary disk, you need to define a temporary disk. The temporary disk must be the same DASD type that is provided by your installation media and the same size as the minidisk you want to recover. (See the \$ITEMMD\$ \$TABLE\$ on the 2CC disk for the size of the minidisk you want to recover.)

```
define [t3390 or vfb-512] loadaddr mdisksize  
DASD loadaddr DEFINED  
Ready; T=n.nn/n.nn hh:mm:ss
```

loadaddr
Address of the temporary disk.

mdisksize
Size of the minidisk you want to restore.

If you receive the following message:

```
HCPLNM091E DASD loadaddr not defined; temp space not available
```

you must add additional temporary disk space to your system or define a minidisk with the address *loadaddr*. If you define a minidisk, it must be the same DASD type that is provided by your installation media and the same size as the minidisk you want to recover.

4. Continue to the appropriate substep depending on the type of installation media.

- DDR tape, continue to substep 5 on page 212.
- DVD, continue to substep 8 on page 212.

Recover a file or minidisk

5. Attach tape drive (*tapeaddr*) to the MAINT user ID at device address 181.

```
attach tapeaddr * 181
tapeaddr attached to MAINT
Ready; T=n.nn/n.nn hh:mm:ss
```

6. Mount the z/VM system DDR tape on tape drive 181.
7. Restore the chosen minidisk by using the INSTALL command and RECOVER option.

```
install tape (recover mdiskaddr loadaddr          mdiskaddr
                                                    Address of the minidisk to be loaded from the
                                                    z/VM system DDR.

                                                    loadaddr
                                                    Address to which you restore the minidisk.
```

Notes:

- a. If the minidisk belongs to MAINT, *mdiskaddr* is the actual minidisk address. If the minidisk does not belong to MAINT, *mdiskaddr* is the alias address. See the \$ITEMMD\$ \$TABLE\$ on the 2CC disk to determine the alias address.
 - b. To recover a minidisk and overlay the existing disk, you must link the minidisk in write mode. For example, enter the LINK CMSBATCH 195 801 WR command.
 - c. If you want to restore an entire minidisk and overlay the existing minidisk, *loadaddr* is the address at which you have the disk linked.
If the load address (*loadaddr*) is not specified, a temporary disk (T-disk) is created.
 - d. You cannot recover the 2CC minidisk directly to the 2CC minidisk. You can recover the 2CC to an address other than 2CC and copy the files you wish to recover to the 2CC minidisk.
 - e. The INSTALL EXEC requires a full screen terminal with at least 20 lines.
8. Recover the minidisk.

If your installation media was DVD, you could have installed from the DVD or uploaded the contents of the DVD to either an FTP server or VM minidisk. You can use the FTP server or VM minidisk if they are still available, otherwise use the DVD.

- a. Run INSTPIPE

```
instpipe
```

- b. Recover from the DVD or FTP server:

```
pipe ftpget -h IPaddress -u userID -p password -d ftpdrct -v BEF -DVDEOF -f dddcuu* |UNPACK|
restcmd loadaddr
```

<i>IPaddress</i>	IP address or FTP HOSTNAME.	<i>cuu*</i>	Address of the minidisk to be recovered from the DVD, with an asterisk (*) appended to the end.
<i>userID</i>		<i>restcmd</i>	ECKDREST for 3390 or MDREST for FBA.
<i>password</i>	User ID and password used to log on to the FTP server.	<i>loadaddr</i>	Address to which you are restoring the minidisk.
<i>ftpdrcr</i>	Path to the DVD drive or server directory. If using a DVD drive, append /CPDVD to the end of the path.		
<i>ddd</i>	CKD for 3390 or FBA for FBA.		

Notes:

- 1) To recover a minidisk and overlay the existing disk, you must link the minidisk in write mode. For example, enter the LINK CMSBATCH 195 801 WR command.
- 2) If the minidisk belongs to MAINT, *cuu* is the actual minidisk address. If the minidisk does not belong to MAINT, *cuu* is the alias address. See the \$ITEMMD\$ \$TABLE\$ on the 2CC disk to determine the alias address.
- 3) If you want to recover an entire minidisk and overlay the existing minidisk, *loadaddr* is the address at which you have the disk linked. If *loadaddr* is not specified, a temporary disk (T-disk) is created.

C. Recover from a VM minidisk. Access the VM minidisk address as C.

access <i>diskaddr c</i>	
Ready; T= <i>n.nn/n.nn hh:mm:ss</i>	
pipe <i>dvddecod dddcuu image c UNPACK restcmd loadaddr</i>	
<i>ddd</i>	<i>restcmd</i>
CKD for 3390 or FBA for FBA.	ECKDREST for 3390 or MDREST for FBA.
<i>cuu</i>	<i>loadaddr</i>
Address of the minidisk to be recovered from the DVD.	Address to which you are recovering the minidisk.

Notes:

- 1) To recover a minidisk and overlay the existing disk, you must link the minidisk in write mode. For example, enter the LINK CMSBATCH 195 801 WR command.
- 2) If the minidisk belongs to MAINT, *cuu* is the actual minidisk address. If the minidisk does not belong to MAINT, *cuu* is the alias address. See the \$ITEMMD\$ \$TABLE\$ on the 2CC disk to determine the alias address.
- 3) If you want to recover an entire minidisk and overlay the existing minidisk, *loadaddr* is the address at which you have the disk linked. If *loadaddr* is not specified, a temporary disk (T-disk) is created.

9. If you restored the minidisk to a temporary disk, copy the file or files that you want to recover from the temporary disk to the target disk.

access <i>loadaddr fm-1</i>	<i>loadaddr</i>
Ready; T= <i>n.nn/n.nn hh:mm:ss</i>	Address of the temporary disk.
	<i>fm-1</i>
	Any available file mode.

Recover a file or minidisk

access *mdiskaddr fm-2*
Ready; T=*n.nn/n.nn hh:mm:ss*

copyfile *fn ft fm-1 = = fm-2 (olddate*
Ready; T=*n.nn/n.nn hh:mm:ss*

mdiskaddr
Address of the target minidisk. If you loaded z/VM to the file pool, *mdiskaddr* is the directory to which the minidisks were copied. See MOVE2SFS \$TABLE\$ for a list of minidisks and directories.

fm-2
Any available file mode.

fn File name of the file you want to recover.

ft File type of the file you want to recover. Repeat the COPYFILE command for each file you want to recover.

Appendix I. Using an Integrated 3270 Console for Installation

Perform the following steps to install the z/VM system DDR in a new system environment using an integrated 3270 console on the HMC.

1. Open the CPC Image Work Area pane.
 - a. In the Hardware Management Console Workplace window, double-click the **Task List** icon in the Views pane.
 - b. In the Task List Work Area pane, double-click the **CPC Recovery** icon.
 - c. In the Views pane, double-click the **Groups** icon.
 - d. In the Groups Work Area pane, double-click the **CPC Images** icon.
2. IPL the tape drive to load ICKDSF.
 - a. In the CPC Images Work Area pane, select the LPAR you are going to use for installation.
 - b. In the Recovery pane, double-click the **Load** icon. The Load window opens.
 - c. In the Load window, ensure that a Load Type of "Normal" is selected, enter the device address of your tape drive in the **Load address** field, and enter CNSLSCLP in the **Load parameter** field.
 - d. Click **OK**. The Load Task Confirmation prompt is displayed.
 - e. Click **Yes** to continue.
 - f. Messages indicating the status of the load are displayed in the Load Progress window. When a message is displayed indicating the load is successful, click **OK** to close the window.
 - g. In the Hardware Management Console Workplace window, double-click the **Operating System Messages** icon in the Recovery pane. The Operating System Messages window opens. ICKDSF will load in the Operating System Messages window. It might take a few minutes for the messages to appear.
 - h. Go back to "Step 1. Restore the Initial Installation System (IIS)" on page 12 and follow substeps 6 through 11 to use ICKDSF to initialize, format, and label the packs needed for installation. Return here when instructed.
 - i. Close the Operating System Messages window.
3. Open an integrated 3270 console and IPL the tape drive to load the DDR program. The Integrated 3270 Console window must remain open, even if it is in the background.
 - a. In the Hardware Management Console Workplace window, select the LPAR you are using for installation in the CPC Images Work Area pane.
 - b. In the Recovery pane, double-click the **Integrated 3270 Console** icon. The Integrated 3270 Console window for that LPAR opens.
 - c. In the Hardware Management Console Workplace window, select the LPAR you are using for installation in the CPC Images Work Area pane again.
 - d. In the Recovery pane, double-click the **Load** icon. The Load window opens.
 - e. In the Load window, enter the device address of your tape drive in the **Load address** field and enter SYSG in the **Load parameter** field. Ensure the **Load parameter** field is empty before entering SYSG.
 - f. Click **OK**. The Load Task Confirmation prompt is displayed.
 - g. Click **Yes** to continue.

Using an integrated 3270 console for installation

- h. Messages indicating the status of the load are displayed in the Load Progress window. When a message is displayed indicating the load is successful, click **OK** to close the window.
 - i. Click on the Integrated 3270 Console window to bring it to the foreground. The DDR program will be displayed in the Integrated 3270 Console window.
 - j. Go back to “Step 1. Restore the Initial Installation System (IIS)” on page 12 and follow substeps 12 and 13 to use DDR to load the IIS. Return here when instructed.
 - k. Keep the Integrated 3270 Console window open in the background.
4. IPL the tape drive to load ICKDSF again.

Note: After the DDR program completes the restore, the tape is rewound to the beginning. If you have problems IPLing the tape, you might need to mount the tape again.

- a. In the Hardware Management Console Workplace window, select the LPAR you are using for installation in the CPC Images Work Area pane.
 - b. In the Recovery pane, double-click the **Load** icon. The Load window opens.
 - c. In the Load window, enter the device address of your tape drive in the **Load address** field and enter CNSLSCLP in the **Load parameter** field.
 - d. Click **OK**. The Load Task Confirmation prompt is displayed.
 - e. Click **Yes** to continue.
 - f. Messages indicating the status of the load are displayed in the Load Progress window. When a message is displayed indicating the load is successful, click **OK** to close the window.
 - g. In the Hardware Management Console Workplace window, double-click the **Operating System Messages** icon in the Recovery pane. The Operating System Messages window opens. ICKDSF will load in the Operating System Messages window. It might take a few minutes for the messages to appear.
 - h. Go back to “Step 1. Restore the Initial Installation System (IIS)” on page 12 and follow substeps 14 through 16 to use ICKDSF to allocate your paging and spool space, and allocate the remainder of your 610RES pack if necessary. Return here when instructed.
 - i. Close the Operating System Messages window.
5. IPL the 610RES to start the IIS portion of the installation.
- a. In the Hardware Management Console Workplace window, select the LPAR you are using for installation in the CPC Images Work Area pane.
 - b. In the Recovery pane, double-click the **Load** icon. The Load window opens.
 - c. In the Load window, enter the DASD address of your 610RES volume in the **Load address** field and enter SYSG in the **Load parameter** field.
 - d. Click **OK**. The Load Task Confirmation prompt is displayed.
 - e. Click **Yes** to continue.
 - f. Messages indicating the status of the load are displayed in the Load Progress window. When a message is displayed indicating the load is successful, click **OK** to close the window.
 - g. Click on the Integrated 3270 Console window to bring it to the foreground. The Stand Alone Program Loader (SAPL) panel will be displayed in the Integrated 3270 Console window.
 - h. Go back to “Step 2. IPL z/VM IIS” on page 19 and continue with substep 2 to complete the installation.

Using an integrated 3270 console for installation

Note: Use CONS=SYSG in place of CONS=*consaddr* on the SAPL panel before pressing F10 to load.

Using an integrated 3270 console for installation

Appendix J. Using a Terminal Emulator to Upload Files from a DVD

Note: Using a terminal emulator to upload files from a DVD can take several hours to complete.

The following procedure will guide you through using IBM Personal Communications to upload files from the z/VM system DVD and the RSU DVD to a VM minidisk. If Personal Communications is not your preferred terminal emulator, this procedure can be used as a model for using the upload function provided with your preferred terminal emulator.

Requirement: Files must be uploaded with a **fixed** record format, a logical record length of **1028**, and a **binary** transfer type. These options must be used to ensure file attributes are maintained.

1. Start a new Personal Communications session and log on to a userid with access to the minidisk where you will transfer the DVD files.
2. If you have already set up a “dvdbinary” transfer type, skip to substep 3. Otherwise, create a new transfer type called “dvdbinary”.

a. From the **Edit** menu, click **Preferences** then **Transfer**.

b. In the File Transfer Settings window, click the **General** tab and verify that the **Host Type** is **VM/CMS**. If not, select **VM/CMS** from the **Host Type** list.

c. Click the **VM** tab.

- 1) In the **Transfer Type** field, enter “dvdbinary”.
- 2) Select **Fixed** in the **Record Format** list.
- 3) In the **Logical Record Length** field, enter “1028”.
- 4) Click **Save**.
- 5) Click **OK**.

3. Load the z/VM system DVD in the DVD drive.

Note: If your DVD drive is not labeled drive letter D, copy the 610prod.srl file from the DVD to your workstation. Open the file, and change “D:” to match your DVD drive letter for each entry. Save the modified file and use it instead of the copy on the DVD for the following steps.

4. Upload the contents of the DVD to the VM minidisk (previously accessed as file mode W).

a. Set messages off in your VM session:

```
set msg off
set emsg off
set imsg off
set wng off
```

b. From the **Actions** menu, click **Send File To Host**.

c. In the Send Files to Host window, click **Open List**.

- 1) In the Open File-Transfer List File window, navigate to the CPDVD directory on the DVD and select the 610prod.srl file.

Note: If you created a modified 610prod.srl file in the previous substep, navigate to the location on your workstation where the modified file is saved and select it instead.

- 2) Click **Open**. Each file to be copied is added to the transfer list.

Using a terminal emulator to upload files from a DVD

- d. Click **Send**.
5. Repeat this procedure using the RSU DVD. Substitute one of the following *.srl files in place of the 610prod.srl file used for the z/VM system DVD.

If installing to . . .	Then substitute . . .
3390	61ckdrsu.srl
FBA	61fbarsu.srl

6. When all files have been transferred, restore your message settings in your VM session:

```
set msg on
set emsg on
set imsg on
set wng on
```

Notices

This information was developed for products and services offered in the U.S.A. IBM may not offer the products, services, or features discussed in this document in all countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing
IBM Corporation
North Castle Drive
Armonk, New York 10504-1785
U.S.A.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

IBM World Trade Asia Corporation
Licensing
2-31 Roppongi 3-chome, Minato-ku
Tokyo 106-0032, Japan

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law: INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Corporation
Mail Station P300
2455 South Road
Poughkeepsie, New York 12601-5400
U.S.A.
Attention: Information Request

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

Any performance data contained herein was determined in a controlled environment. Therefore, the results obtained in other operating environments may vary significantly. Some measurements may have been made on development-level systems and there is no guarantee that these measurements will be the same on generally available systems. Furthermore, some measurement may have been estimated through extrapolation. Actual results may vary. Users of this document should verify the applicable data for their specific environment.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

All statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

This information may contain examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

COPYRIGHT LICENSE:

This information may contain sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs.

Trademarks

IBM, the IBM logo, and ibm.com are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the Web at "Copyright and trademark information" at www.ibm.com/legal/copytrade.shtml

Adobe is a registered trademark of Adobe Systems Incorporated in the United States, and/or other countries.

Java and all Java-based trademarks and logos are trademarks of Sun Microsystems, Inc. in the United States, other countries, or both.

Linux is a registered trademark of Linus Torvalds in the United States, other countries, or both.

Microsoft and Windows are trademarks of Microsoft Corporation in the United States, other countries, or both.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Other company, product, or service names may be trademarks or service marks of others.

Glossary

For a list of z/VM terms and their definitions, see *z/VM: Glossary*.

The z/VM glossary is also available through the online z/VM HELP Facility. For example, to display the definition of the term “dedicated device”, issue the following HELP command:

```
help glossary dedicated device
```

While you are in the glossary help file, you can do additional searches:

- To display the definition of a new term, type a new HELP command on the command line:

```
help glossary newterm
```

This command opens a new help file inside the previous help file. You can repeat this process many times. The status area in the lower right corner of the screen shows how many help files you have open. To close the current file, press the Quit key (PF3/F3). To exit from the HELP Facility, press the Return key (PF4/F4).

- To search for a word, phrase, or character string, type it on the command line and press the Clocate key (PF5/F5). To find other occurrences, press the key multiple times.

The Clocate function searches from the current location to the end of the file. It does not wrap. To search the whole file, press the Top key (PF2/F2) to go to the top of the file before using Clocate.

Bibliography

See the following publications for additional information about z/VM. For abstracts of the z/VM publications, see *z/VM: General Information*.

Where to Get z/VM Information

z/VM product information is available from the following sources:

- z/VM Information Center at publib.boulder.ibm.com/infocenter/zvm/v6r1/index.jsp
- z/VM Internet Library at www.ibm.com/eserver/zseries/zvm/library/
- IBM Publications Center at www.elink.ibmink.ibm.com/publications/servlet/pbi.wss
- *IBM Online Library: z/VM Collection on DVD*, SK5T-7054

z/VM Base Library

Overview

- *z/VM: General Information*, GC24-6193
- *z/VM: Glossary*, GC24-6195
- *z/VM: License Information*, GC24-6200

Installation, Migration, and Service

- *z/VM: Guide for Automated Installation and Service*, GC24-6197
- *z/VM: Migration Guide*, GC24-6201
- *z/VM: Service Guide*, GC24-6232
- *z/VM: VMSES/E Introduction and Reference*, GC24-6243

Planning and Administration

- *z/VM: CMS File Pool Planning, Administration, and Operation*, SC24-6167
- *z/VM: CMS Planning and Administration*, SC24-6171
- *z/VM: Connectivity*, SC24-6174
- *z/VM: CP Planning and Administration*, SC24-6178
- *z/VM: Getting Started with Linux on System z*, SC24-6194
- *z/VM: Group Control System*, SC24-6196

- *z/VM: I/O Configuration*, SC24-6198
- *z/VM: Running Guest Operating Systems*, SC24-6228
- *z/VM: Saved Segments Planning and Administration*, SC24-6229
- *z/VM: Secure Configuration Guide*, SC24-6230
- *z/VM: TCP/IP LDAP Administration Guide*, SC24-6236
- *z/VM: TCP/IP Planning and Customization*, SC24-6238
- *z/OS and z/VM: Hardware Configuration Manager User's Guide*, SC33-7989

Customization and Tuning

- *z/VM: CP Exit Customization*, SC24-6176
- *z/VM: Performance*, SC24-6208

Operation and Use

- *z/VM: CMS Commands and Utilities Reference*, SC24-6166
- *z/VM: CMS Pipelines Reference*, SC24-6169
- *z/VM: CMS Pipelines User's Guide*, SC24-6170
- *z/VM: CMS Primer*, SC24-6172
- *z/VM: CMS User's Guide*, SC24-6173
- *z/VM: CP Commands and Utilities Reference*, SC24-6175
- *z/VM: System Operation*, SC24-6233
- *z/VM: TCP/IP User's Guide*, SC24-6240
- *z/VM: Virtual Machine Operation*, SC24-6241
- *z/VM: XEDIT Commands and Macros Reference*, SC24-6244
- *z/VM: XEDIT User's Guide*, SC24-6245
- *CMS/TSO Pipelines: Author's Edition*, SL26-0018

Application Programming

- *z/VM: CMS Application Development Guide*, SC24-6162
- *z/VM: CMS Application Development Guide for Assembler*, SC24-6163
- *z/VM: CMS Application Multitasking*, SC24-6164
- *z/VM: CMS Callable Services Reference*, SC24-6165
- *z/VM: CMS Macros and Functions Reference*, SC24-6168

- *z/VM: CP Programming Services*, SC24-6179
- *z/VM: CPI Communications User's Guide*, SC24-6180
- *z/VM: Enterprise Systems Architecture/ Extended Configuration Principles of Operation*, SC24-6192
- *z/VM: Language Environment User's Guide*, SC24-6199
- *z/VM: OpenExtensions Advanced Application Programming Tools*, SC24-6202
- *z/VM: OpenExtensions Callable Services Reference*, SC24-6203
- *z/VM: OpenExtensions Commands Reference*, SC24-6204
- *z/VM: OpenExtensions POSIX Conformance Document*, GC24-6205
- *z/VM: OpenExtensions User's Guide*, SC24-6206
- *z/VM: Program Management Binder for CMS*, SC24-6211
- *z/VM: Reusable Server Kernel Programmer's Guide and Reference*, SC24-6220
- *z/VM: REXX/VM Reference*, SC24-6221
- *z/VM: REXX/VM User's Guide*, SC24-6222
- *z/VM: Systems Management Application Programming*, SC24-6234
- *z/VM: TCP/IP Programmer's Reference*, SC24-6239
- *Common Programming Interface Communications Reference*, SC26-4399
- *Common Programming Interface Resource Recovery Reference*, SC31-6821
- *z/OS: IBM Tivoli Directory Server Plug-in Reference for z/OS*, SA76-0148
- *z/OS: Language Environment Concepts Guide*, SA22-7567
- *z/OS: Language Environment Debugging Guide*, GA22-7560
- *z/OS: Language Environment Programming Guide*, SA22-7561
- *z/OS: Language Environment Programming Reference*, SA22-7562
- *z/OS: Language Environment Run-Time Messages*, SA22-7566
- *z/OS: Language Environment Writing ILC Applications*, SA22-7563
- *z/OS MVS Program Management: Advanced Facilities*, SA22-7644
- *z/OS MVS Program Management: User's Guide and Reference*, SA22-7643

Diagnosis

- *z/VM: CMS and REXX/VM Messages and Codes*, GC24-6161
- *z/VM: CP Messages and Codes*, GC24-6177
- *z/VM: Diagnosis Guide*, GC24-6187
- *z/VM: Dump Viewing Facility*, GC24-6191
- *z/VM: Other Components Messages and Codes*, GC24-6207
- *z/VM: TCP/IP Diagnosis Guide*, GC24-6235
- *z/VM: TCP/IP Messages and Codes*, GC24-6237
- *z/VM: VM Dump Tool*, GC24-6242
- *z/OS and z/VM: Hardware Configuration Definition Messages*, SC33-7986

z/VM Facilities and Features

Data Facility Storage Management Subsystem for VM

- *z/VM: DFSMS/VM Customization*, SC24-6181
- *z/VM: DFSMS/VM Diagnosis Guide*, GC24-6182
- *z/VM: DFSMS/VM Messages and Codes*, GC24-6183
- *z/VM: DFSMS/VM Planning Guide*, SC24-6184
- *z/VM: DFSMS/VM Removable Media Services*, SC24-6185
- *z/VM: DFSMS/VM Storage Administration*, SC24-6186

Directory Maintenance Facility for z/VM

- *z/VM: Directory Maintenance Facility Commands Reference*, SC24-6188
- *z/VM: Directory Maintenance Facility Messages*, GC24-6189
- *z/VM: Directory Maintenance Facility Tailoring and Administration Guide*, SC24-6190

Open Systems Adapter/Support Facility

- *System z10, System z9 and eServer zSeries: Open Systems Adapter-Express Customer's Guide and Reference*, SA22-7935
- *System z9 and eServer zSeries 890 and 990: Open Systems Adapter-Express Integrated Console Controller User's Guide*, SA22-7990

- *System z: Open Systems Adapter-Express Integrated Console Controller 3215 Support*, SA23-2247

Performance Toolkit for VM™

- *z/VM: Performance Toolkit Guide*, SC24-6209
- *z/VM: Performance Toolkit Reference*, SC24-6210

RACF® Security Server for z/VM

- *z/VM: RACF Security Server Auditor's Guide*, SC24-6212
- *z/VM: RACF Security Server Command Language Reference*, SC24-6213
- *z/VM: RACF Security Server Diagnosis Guide*, GC24-6214
- *z/VM: RACF Security Server General User's Guide*, SC24-6215
- *z/VM: RACF Security Server Macros and Interfaces*, SC24-6216
- *z/VM: RACF Security Server Messages and Codes*, GC24-6217
- *z/VM: RACF Security Server Security Administrator's Guide*, SC24-6218
- *z/VM: RACF Security Server System Programmer's Guide*, SC24-6219
- *z/VM: Security Server RACROUTE Macro Reference*, SC24-6231

Remote Spooling Communications Subsystem Networking for z/VM

- *z/VM: RSCS Networking Diagnosis*, GC24-6223
- *z/VM: RSCS Networking Exit Customization*, SC24-6224
- *z/VM: RSCS Networking Messages and Codes*, GC24-6225
- *z/VM: RSCS Networking Operation and Use*, SC24-6226
- *z/VM: RSCS Networking Planning and Configuration*, SC24-6227
- *Network Job Entry: Formats and Protocols*, SA22-7539

Prerequisite Products

Device Support Facilities

- *Device Support Facilities: User's Guide and Reference*, GC35-0033

Environmental Record Editing and Printing Program

- *Environmental Record Editing and Printing Program (EREP): Reference*, GC35-0152
- *Environmental Record Editing and Printing Program (EREP): User's Guide*, GC35-0151

Index

A

about this document xi
audience of this information xi

B

backing up
 CMS to tape 134
 CP to DASD 138
 CP to tape 135
 named saved systems to tape 134

C

CMS (Conversational Monitor System)
 saved systems
 backing up to tape 134
conventions and terminology xi
conventions used xi
corequisite information xi
CP (Control Program)
 backing up to DASD 138
 backing up to tape 135

D

DASD (Direct Access Storage Device)
 DDR installation worksheet 7
 DVD installation worksheet 64
 restoring IIS minidisks 12, 40, 68, 73, 75, 110, 112
 SCSI device definition worksheet (DVD
 Installation) 64
 used for installation 7, 64
DASD Dump/Restore Program (DDRXA)
 See DDRXA (DASD Dump/Restore Program)
DDR installation TCP/IP configuration worksheet 8
DDRXA (DASD Dump/Restore Program)
 backup system to tape 135, 140
 restoring the system to disk 209
DETERSE
 using 51, 187
Device Support Facilities (ICKDSF)
 See ICKDSF (Device Support Facilities)
diagram for selecting z/VM system DDR installation
 procedure 3, 59
DVD installation TCP/IP configuration worksheet 65

E

Environmental Recording Editing and Printing Program
(EREP)
 See EREP (Environmental Recording Editing and
 Printing Program)
EREP (Environmental Recording Editing and Printing
Program)
 product information 179

examples, layout of xi

F

file recovery 211
format of this information xi

I

ICKDSF (Device Support Facilities)
 backup system to tape 141
 product information 179
IIS (Initial Installation System)
 IPL 19, 42, 68, 78, 116
 loading 12, 16
 restoring to disk 12, 40, 68, 73, 75, 110, 112
Initial Installation System (IIS)
 See IIS (Initial Installation System)
installation
 procedures
 choosing 3, 59
 saved segments 205
installation worksheet 7, 64
installing
 from a 3270 console
 steps for 215
INSTIIS EXEC
 using 40
INSTPLAN EXEC
 using 23, 38, 71, 108
INSTVM EXEC
 system DDR, loading 25, 46
 System image, loading 82, 120
intended audience xi
IPL your initial system
 installation procedure 1 19, 68
 installation procedure 2 42, 78, 116

L

licensed products and features, preinstalled 179
 Directory Maintenance Facility 179
 EREP 179
 HCD and HCM 180
 ICKDSF 180
 OSA/SF 180
 Performance Toolkit for VM 181
 RACF Security Server 181
 RSCS Networking 181
 TCP/IP 182
loader panel, sample stand-alone 19, 42, 78, 116, 153,
158, 170
LOCALMOD
 using 199

M

- MIGR51D EXEC
 - using 197
- MIGRATE EXEC
 - using 161
- minidisk
 - formatting
 - installation procedure 1 14
 - installation procedure 2 40
 - recovering 211

O

- overview
 - z/VM system DDR installation procedures 3, 59

P

- panels, installation
 - Stand-Alone Program Loader
 - z/VM system DDR install example 19, 42, 78, 116, 153, 158, 170
- prerequisites to using this information xi
- procedure 1, z/VM system DDR installation
 - CMS nucleus defaults 203
 - CP system configuration file defaults 203
 - GCS defaults 204
 - initialize DASD 12, 68
 - IPL z/VM Initial Installation System 19, 68
 - restore IIS to DASD 12, 68
 - run INSTALL EXEC 25, 46, 82, 120
 - segments on the z/VM system 205
- procedure 2, z/VM system DDR installation
 - CMS nucleus defaults 203
 - CP system configuration file defaults 203
 - format DASD 40
 - from a VM minidisk 100
 - GCS defaults 204
 - IPL new z/VM System 78, 116
 - IPL z/VM Initial Installation System 42
 - loading installation tools 36
 - loading installation tools 92, 96
 - restore IIS to DASD 40, 73, 75, 110, 112
 - run INSTALL EXEC 25, 46, 82, 120
 - segments on the z/VM system 205
 - selecting items to load 38, 71, 108
- procedures, layout of xi
- production, placing product into 31, 53, 87, 125
- purpose of this document xi
- PUT2PROD EXEC 31, 53

Q

- QUERY NSS command
 - saved segment definitions 205

R

- recovering a file 211
- recovering a minidisk 211

- recovery file pool
 - defaults 205
- restoring
 - IIS minidisks 12, 40, 68, 73, 75, 110, 112

S

- SAPL (Stand-Alone Program Loader)
 - loader panel 19, 42, 78, 116, 153, 158, 170
 - loading 1st level 19
- service 85, 123, 183
 - install preventative (RSU) or corrective (COR) 185
 - local service and modifications, apply or rework 199
 - placing into production 185
- SERVICE EXEC 29, 50
- service, covered components, features, and products 183
- setting TOD clock 20, 44, 80, 118, 172
 - setting 154, 160
- SFS (Shared File System)
 - file pool definition file defaults 205
- Shared File System
 - See SFS (Shared File System)
- stand-alone dump tape, creating 143
- stand-alone loader panel 19, 42, 78, 116, 153, 158, 170
- Stand-Alone Program Loader (SAPL)
 - See SAPL (Stand-Alone Program Loader)
- summary of
 - z/VM system DDR installation procedures 3, 59
- system console address
 - primary
 - DDR installation worksheet 7
 - DVD installation worksheet 64
 - SCSI device definition worksheet (DVD Installation) 64
 - specifying during IPL 19
- system DDR backup procedure
 - See z/VM system DDR backup procedure
- system DDR installation procedure
 - See z/VM system DDR installation procedure
- system generation
 - backing up
 - named saved systems to tape 134
 - system to DASD 138
 - system to tape 135
 - initializing DASD packs 13
 - initializing system residence pack 13
 - restoring Initial Installation System to disk
 - installation procedure 1 12, 68
 - installation procedure 2 40, 73, 75, 110, 112

T

- tasks
 - Setting up VMSES/E Licensed Products to use the SERVICE
 - steps for 193
- terminal emulator
 - upload file from DVD
 - steps for 219

terminology used xi
TOD (time-of-day) clock
 setting 20, 44, 80, 118, 154, 160, 172
two-column format xi

U

user entries, layout of xi
user file pool
 defaults 205
using this information xi

V

VMFPLC2 command 37
VMSERVER DMSPARMS 205
VSAM
 See VSE/VSAM (Virtual Storage Extended/Virtual
 Storage Access Method)
VSE/VSAM (Virtual Storage Extended/Virtual Storage
 Access Method)
 default user IDs requiring 204

W

worksheets
 DDR installation 7
 DDR installation TCP/IP configuration 8
 DVD installation 64
 DVD installation TCP/IP configuration 65

Z

z/VM system DDR backup procedure
 back up named saved systems 134
 restore z/VM system backup copy 207, 209
 store backup copy of z/VM system on tape 135,
 138
z/VM system DDR installation procedure
 installation worksheet 7, 64
 overview of procedures 3, 59
 procedure 1
 CMS nucleus defaults 203
 CP system configuration file defaults 203
 GCS defaults 204
 initialize DASD 12, 68
 IPL z/VM Initial Installation System 19, 68
 restore IIS to DASD 12, 68
 run INSTALL EXEC 25, 46, 82, 120
 segments on the z/VM system 205
 procedure 2
 CMS nucleus defaults 179, 203
 CP system configuration file defaults 203
 format DASD 40
 from a VM minidisk 100
 GCS defaults 204
 IPL new z/VM System 78, 116
 IPL z/VM Initial Installation System 42
 loading installation tools 36, 92, 96
 restore IIS to DASD 40, 73, 75, 110, 112

z/VM system DDR installation procedure (*continued*)
 procedure 2 (*continued*)
 run INSTALL EXEC 25, 46, 82, 120
 segments on the z/VM system 205
 selecting items to load 38, 71, 108
 selecting a procedure 3, 59



Program Number: 5741-A07

Printed in USA

GC24-6197-00

